

IBM Informix SNMP Subagent Guide

IBM Informix Extended Parallel Server, Version 8.4
IBM Informix Dynamic Server, Version 9.4

March 2003
Part No. CT1SVNA

Note:

Before using this information and the product it supports, read the information in the appendix entitled "Notices."

This document contains proprietary information of IBM. It is provided under a license agreement and is protected by copyright law. The information contained in this publication does not include any product warranties, and any statements provided in this manual should not be interpreted as such.

When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

© Copyright International Business Machines Corporation 1996, 2003. All rights reserved.

US Government User Restricted Rights—Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Table of Contents

Introduction

In This Introduction	3
About This Manual	3
Types of Users	3
Software Dependencies	4
Assumptions About Your Locale.	4
Demonstration Databases	5
New Features	5
Documentation Conventions	6
Typographical Conventions	6
Icon Conventions	7
Command-Line Conventions	8
Additional Documentation	11
Related Reading	13
Compliance with Industry Standards	14
IBM Welcomes Your Comments	14

Chapter 1

SNMP Concepts

In This Chapter	1-3
Purpose of SNMP	1-3
SNMP Architecture	1-4
SNMP Network Managers	1-5
Master Agents	1-7
Subagents	1-8
Managed Components	1-8
MIBs	1-9

Chapter 2

IBM Informix Implementation of SNMP

In This Chapter	2-3
Purpose of IBM Informix SNMP	2-4
Event Notification	2-4
Data Requests	2-4
Traps	2-5
Information That OnSNMP Provides	2-6
SNMP Standard	2-7
SNMP Architecture	2-7
IBM Informix SNMP Architecture on UNIX	2-7
IBM Informix SNMP Architecture on Windows	2-9
Using SNMP on UNIX	2-11
The runsnmp.ksh Script	2-12
UNIX Master Agents	2-13
UNIX Subagent	2-18
UNIX Server Discovery Process.	2-18
Using SNMP on Windows	2-21
Windows Master Agent	2-22
Windows Subagent	2-23
Windows Server Discovery Process	2-25
SNMP and Extended Parallel Server	2-27
GLS and SNMP	2-28
MIBs	2-29
Application MIB	2-29
RDBMS MIB	2-30
Informix Private MIB	2-31
Online MIB.	2-32
XPS MIB.	2-32
MIB Objects	2-32
Table Indexing	2-33
Numeric Index Values	2-33
Alphabetical Index Values	2-34
Refresh Control Value	2-35
Files Installed for SNMP	2-36
Files Installed on UNIX	2-36
Files Installed on Windows	2-37

Chapter 3

MIB Reference

In This Chapter	3-3
Application MIB	3-6
RDBMS MIB	3-8
rdbmsDbInfoTable.	3-8
rdbmsDbLimitedResourceTable	3-9
rdbmsDbParamTable	3-9
rdbmsDbTable	3-9
rdbmsRelTable	3-10
rdbmsSrvInfoTable	3-11
rdbmsSrvLimitedResourceTable	3-13
rdbmsSrvParamTable.	3-14
rdbmsSrvTable	3-15
rdbmsTraps	3-16
Online MIB in the Informix Private MIB	3-17
onActiveBarTable	3-17
onActiveTableTable	3-18
onBarTable	3-20
onChunkTable	3-21
onDatabaseTable	3-23
onDbospaceTable	3-24
onErQueueTable	3-26
onErSiteTable	3-27
onFragmentTable	3-29
onLockTable	3-31
onLogicalLogTable	3-32
onPhysicalLogTable	3-33
onServerTable	3-34
onSessionTable	3-37
onSqlHostTable	3-40
onTableTable.	3-41
onXpsTable	3-44
XPS MIB in the Informix Private MIB	3-45
xpsCogroupMemberTable	3-45
xpsCogroupTable	3-45
xpsCoserverTable	3-46
xpsDbsliceDbospaceTable.	3-47
xpsDbsliceTable.	3-48

Appendix A	Notices
	Glossary
	Index

Introduction

In This Introduction	3
About This Manual.	3
Types of Users	3
Software Dependencies	4
Assumptions About Your Locale.	4
Demonstration Databases	5
New Features.	5
Documentation Conventions	6
Typographical Conventions	6
Icon Conventions	7
Comment Icons	7
Feature, Product, and Platform Icons	8
Command-Line Conventions	8
How to Read a Command-Line Diagram	10
Additional Documentation	11
Related Reading.	13
Compliance with Industry Standards	14
IBM Welcomes Your Comments	14

In This Introduction

This introduction provides an overview of the information in this manual and describes the conventions it uses.

About This Manual

This manual describes the Simple Network Management Protocol (SNMP) and the software that you need to use SNMP to monitor and manage Informix database servers, coservers, and databases.

Types of Users

This manual is written for the following users:

- Database server administrators
- Backup operators
- Performance engineers

This manual assumes that you have the following background:

- A working knowledge of your computer, your operating system, and the utilities that your operating system provides
- Some experience with database server administration, operating-system administration, or network administration

Software Dependencies

This manual assumes that you are using one of the following database servers:

- IBM Informix Extended Parallel Server, Version 8.4
- IBM Informix Dynamic Server, Version 9.4

You must install additional software to use the IBM Informix implementation of SNMP. For specific requirements, see [Chapter 2, “IBM Informix Implementation of SNMP.”](#)

Assumptions About Your Locale

IBM Informix products can support many languages, cultures, and code sets. All culture-specific information is brought together in a single environment, Global Language Support (GLS) locale.

This manual assumes that you use the U.S. 8859-1 English locale as the default locale. The default is **en_us.8859-1** (ISO 8859-1) on UNIX platforms or **en_us.CP1252** (Microsoft **1252**) for Windows environments. This locale supports U.S. English format conventions for dates, times, and currency, and also supports the ISO 8859-1 or Microsoft **1252** code set, which includes the ASCII code set plus many 8-bit characters such as é, è, and ñ.

If you plan to use nondefault characters in your data or your SQL identifiers, or if you want to conform to the nondefault collation rules of character data, you need to specify the appropriate nondefault locale.

For instructions on how to specify a nondefault locale, additional syntax, and other considerations related to GLS locales, see the *IBM Informix GLS User's Guide*.



Important: *SNMPv1 and SNMPv2 do not recognize non-English code sets. For more information, see “GLS and SNMP” on page 2-28.*

Demonstration Databases

The DB-Access utility, which is provided with your Informix database server products, includes one or more of the following demonstration databases:

- The **stores_demo** database illustrates a relational schema with information about a fictitious wholesale sporting-goods distributor. Many examples in IBM Informix manuals are based on the **stores_demo** database.
- The **sales_demo** database illustrates a dimensional schema for data-warehousing applications. For conceptual information about dimensional data modeling, see the *IBM Informix Database Design and Implementation Guide*. ♦
- The **superstores_demo** database illustrates an object-relational schema. The **superstores_demo** database includes examples of extended data types, type and table inheritance, and user-defined routines. ♦

For information about how to create and populate the demonstration databases, see the *IBM Informix DB-Access User's Guide*. For descriptions of the databases and their contents, see the *IBM Informix Guide to SQL: Reference*.

The scripts that you use to install the demonstration databases reside in the **\$INFORMIXDIR/bin** directory on UNIX platforms and in the **%INFORMIXDIR%\bin** directory in Windows environments.

New Features

For a comprehensive list of new features for your database server, see the *Getting Started Guide*.

XPS

IDS

Documentation Conventions

This section describes the conventions that this manual uses. These conventions make it easier to gather information from this and other volumes in the documentation set.

The following conventions are discussed:

- Typographical conventions
- Icon conventions
- Command-line conventions

Typographical Conventions

This manual uses the following conventions to introduce new terms, illustrate screen displays, describe command syntax, and so forth.

Convention	Meaning
KEYWORD	All primary elements in a programming language statement (keywords) appear in uppercase letters in a serif font.
<i>italics</i> <i>italics</i> <i>italics</i>	Within text, new terms and emphasized words appear in italics. Within syntax and code examples, variable values that you are to specify appear in italics.
boldface <i>boldface</i>	Names of program entities (such as classes, events, and tables), environment variables, file and pathnames, and interface elements (such as icons, menu items, and buttons) appear in boldface.
monospace <i>monospace</i>	Information that the product displays and information that you enter appear in a monospace typeface.

(1 of 2)



Convention	Meaning
KEYSTROKE	Keys that you are to press appear in uppercase letters in a sans serif font.
◆	This symbol indicates the end of one or more product- or platform-specific paragraphs.
→	This symbol indicates a menu item. For example, “Choose Tools→Options ” means choose the Options item from the Tools menu.
(2 of 2)	




Tip: When you are instructed to “enter” characters or to “execute” a command, immediately press RETURN after the entry. When you are instructed to “type” the text or to “press” other keys, no RETURN is required.

Icon Conventions

Throughout the documentation, you will find text that is identified by several different types of icons. This section describes these icons.






Comment Icons

Comment icons identify three types of information, as the following table describes. This information always appears in italics.

Icon	Label	Description
	Warning:	Identifies paragraphs that contain vital instructions, cautions, or critical information
	Important:	Identifies paragraphs that contain significant information about the feature or operation that is being described
	Tip:	Identifies paragraphs that offer additional details or shortcuts for the functionality that is being described

Feature, Product, and Platform Icons

Feature, product, and platform icons identify paragraphs that contain feature-specific, product-specific, or platform-specific information.

Icon	Description
	Identifies information that relates to the IBM Informix Global Language Support (GLS) feature
	Identifies information that is specific to IBM Informix Dynamic Server
	Identifies information that is specific to UNIX platforms
	Identifies information that is specific to the Windows environment
	Identifies information or syntax that is specific to IBM Informix Extended Parallel Server

These icons can apply to an entire section or to one or more paragraphs within a section. If an icon appears next to a section heading, the information that applies to the indicated feature, product, or platform ends at the next heading at the same or higher level. A ♦ symbol indicates the end of feature-, product-, or platform-specific information that appears within one or more paragraphs within a section.




Command-Line Conventions

This section defines and illustrates the format of commands that are available in IBM Informix products. These commands have their own conventions, which might include alternative forms of a command, required and optional parts of the command, and so forth.

Each diagram displays the sequences of required and optional elements that are valid in a command. A diagram begins at the upper-left corner with a command. It ends at the upper-right corner with a vertical line. Between these points, you can trace any path that does not stop or back up. Each path describes a valid form of the command. You must supply a value for words that are in *italics*.

You might encounter one or more of the following elements on a command-line path.

Element	Description
command	This required element is usually the product name or other short word that invokes the product or calls the compiler or preprocessor script for a compiled IBM Informix product. It might appear alone or precede one or more options. You must spell a command exactly as shown and use lowercase letters.
<i>variable</i>	A word in italics represents a value that you must supply, such as a database, file, or program name. A table following the diagram explains the value.
-flag	A flag is usually an abbreviation for a function, menu, or option name, or for a compiler or preprocessor argument. You must enter a flag exactly as shown, including the preceding hyphen.
.ext	A filename extension, such as .sql or .cob , might follow a variable that represents a filename. Type this extension exactly as shown, immediately after the name of the file. The extension might be optional in certain products.
(. , ; + * - /)	Punctuation and mathematical notations are literal symbols that you must enter exactly as shown.
' '	Single quotes are literal symbols that you must enter as shown.
<div>Privileges p. 5-17</div> <div>Privileges</div>	A reference in a box represents a subdiagram. Imagine that the subdiagram is spliced into the main diagram at this point. When a page number is not specified, the subdiagram appears on the same page.
— ALL —	A shaded option is the default action.
→ →	Syntax within a pair of arrows indicates a subdiagram.
—	The vertical line terminates the command.


Element	Description
	A branch below the main path indicates an optional path. (Any term on the main path is required, unless a branch can circumvent it.)
	A loop indicates a path that you can repeat. Punctuation along the top of the loop indicates the separator symbol for list items.
	A gate ($\sqrt{3}$) on a path indicates that you can only use that path the indicated number of times, even if it is part of a larger loop. You can specify <i>size</i> no more than three times within this statement segment.

(2 of 2)

How to Read a Command-Line Diagram

Figure 1 shows a command-line diagram that uses some of the elements that are listed in the previous table.

Figure 1
Example of a Command-Line Diagram



To construct a command correctly, start at the top left with the command. Follow the diagram to the right, including the elements that you want. The elements in the diagram are case sensitive.

Figure 1 illustrates the following steps:

1. Type `setenv`.
2. Type `INFORMIXC`.
3. Supply either a compiler name or a pathname.
After you choose *compiler* or *pathname*, you come to the terminator. Your command is complete.
4. Press RETURN to execute the command.

Additional Documentation

IBM Informix Dynamic Server documentation is provided in a variety of formats:

- **Online manuals.** The IBM Informix Online Documentation site at <http://www.ibm.com/software/data/informix/pubs/library/> contains manuals for your use. This Web site enables you to print chapters or entire books.
- **Online help.** IBM Informix online help, provided with each graphical user interface (GUI), displays information about those interfaces and the functions that they perform. Use the help facilities that each GUI provides to display the online help.

This facility can provide context-sensitive help, an error message reference, language syntax, and more.
- Documentation notes, release notes, and machine notes are located in the directory where the product is installed. The following table describes these files.

UNIX

On UNIX platforms, the following online files appear in the \$INFORMIXDIR/release/en_us/0333 directory.

Online File	Purpose
ids_snmp_docnotes_9.40.html xps_snmp_docnotes_8.40.html	The documentation notes file for your version of this manual describes topics that are not covered in the manual or that were modified since publication.
ids_unix_release_notes_9.40.html ids_unix_release_notes_9.40.txt xps_release_notes_8.40.html xps_release_notes_8.40.txt	The release notes file describes feature differences from earlier versions of IBM Informix products and how these differences might affect current products. This file also contains information about any known problems and their workarounds.
ids_machine_notes_9.40.txt xps_machine_notes_8.40.txt	The machine notes file describes any special actions that you must take to configure and use IBM Informix products on your computer. Machine notes are named for the product described.



Windows

The following items appear in the **Informix** folder. To display this folder, choose **Start→Programs→Informix→ Documentation Notes or Release Notes** from the task bar.

Program Group Item	Description
Documentation Notes	This item includes additions or corrections to manuals with information about features that might not be covered in the manuals or that have been modified since publication.
Release Notes	This item describes feature differences from earlier versions of IBM Informix products and how these differences might affect current products. This file also contains information about any known problems and their workarounds.

Machine notes do not apply to Windows platforms. ♦

- **Error message files.** IBM Informix software products provide ASCII files that contain error messages and their corrective actions.

To read the error messages on UNIX, you can use the **finderr** command to display the error messages online. ♦

To read error messages and corrective actions on Windows, use the **Informix Error Messages** utility. To display this utility, choose **Start→Programs→Informix** from the task bar. ♦

UNIX

Windows

Related Reading

For a list of publications that provide an introduction to database servers and operating-system platforms, refer to your *Getting Started Guide*.

Compliance with Industry Standards

The American National Standards Institute (ANSI) has established a set of industry standards for SQL. IBM Informix SQL-based products are fully compliant with SQL-92 Entry Level (published as ANSI X3.135-1992), which is identical to ISO 9075:1992. In addition, many features of Informix database servers comply with the SQL-92 Intermediate and Full Level and X/Open SQL CAE (common applications environment) standards.

IBM Welcomes Your Comments

To help us with future versions of our manuals, let us know about any corrections or clarifications that you would find useful. Include the following information:

- The name and version of your manual
- Any comments that you have about the manual
- Your name, address, and phone number

Send electronic mail to us at the following address:

`docinf@us.ibm.com`

This address is reserved for reporting errors and omissions in our documentation. For immediate help with a technical problem, contact Customer Services.

SNMP Concepts

In This Chapter	1-3
Purpose of SNMP	1-3
SNMP Architecture.	1-4
SNMP Network Managers	1-5
Master Agents	1-7
Subagents.	1-8
Managed Components	1-8
Event Notification	1-8
Data Requests	1-9
Traps	1-9
MIBs	1-9
Naming Conventions	1-9
Hierarchy	1-10

In This Chapter

Simple Network Management Protocol (SNMP) is a published, open standard for network management. SNMP lets hardware and software components on networks provide information to network administrators. This chapter provides a brief introduction to SNMP. For SNMP terms and definitions, see the [Glossary](#).

Purpose of SNMP

Although the original purpose of SNMP was to let network administrators remotely manage an Internet system, the design of SNMP lets network administrators manage applications as well as systems. SNMP provides the following capabilities:


- Hides the underlying system network
- Lets you manage and monitor all network components from one console

SNMP Architecture

As [Figure 1-1](#) illustrates, the SNMP architecture includes the following layers:

- SNMP Network Managers
- Master agents
- Subagents
- Managed components

Figure 1-1
SNMP Architecture



A network can have multiple SNMP Network Managers. Each workstation can have one master agent. The SNMP Network Managers and master agents use SNMP protocols to communicate with each other. Each managed component has a corresponding subagent and MIBs. SNMP does not specify the protocol for communications between master agents and subagents.

SNMP Network Managers

An SNMP Network Manager is a program that asks for information from master agents and displays that information. Most SNMP Network Managers let you select the items to monitor and the form in which to display the information. An SNMP Network Manager typically provides the following features:

- Remote monitoring of managed components
- Low-impact sampling of the performance of a managed component
- Correlation of managed component metrics with related system and network metrics
- Graphical presentation of information

Many hardware and network services have created SNMP Network Managers. For example:


- CA-Unicenter
- Hewlett-Packard Open View
- IBM Netview/6000
- Novell Network Management System
- Sun Solstice
- Tivoli TME 10 NetView

SNMP Network Managers use a connectionless protocol, which means that each exchange between an SNMP Network Manager and a master agent is a separate transaction. A connectionless protocol allows the SNMP Network Manager to perform the following actions:

- Gather information without putting an excessive load on the network
- Function in an environment where heavy traffic can cause network problems

Most SNMP Network Managers provide a graphical user interface (GUI) such as the one that [Figure 1-2](#) illustrates. With this SNMP Network Manager, you select a node to monitor and then choose specific information from a menu.

Figure 1-2
SNMP Network Manager Example



[Figure 1-3](#) shows how an SNMP Network Manager might display information about the databases on a network. In this example, the network has only one database.

```
Feb 17 1999 [ smoke ] : RDBMS-MIB.rdbmsDbTable
KEY = 72000003
rdbmsDbName = CustomerData
rdbmsDbName.72000003 = AnotherData
rdbmsDbPrivateMibOID = 1.3.6.1.4.1.893
rdbmsDbVendorName = Informix Software, Inc.
rdbmsDbName = CustomerData
rdbmsDbContact = John Doe
```

Figure 1-3
*Example of
Monitoring
Information*

Figure 1-4 shows how a different SNMP Network Manager could display the same information.

```
rdbsDbPrivateMibOID.72000003 = 1.3.6.1.4.1.893
rdbsDbVendorName.72000003 = Informix Software, Inc.
rdbsDbName.72000003 = CustomerData
rdbsDbContact.72000003 = John Doe
```

Figure 1-4
*Example of
Monitoring
Information*

In addition to text, an SNMP Network Manager might also display graphs or charts, as Figure 1-5 illustrates.




Figure 1-5
*Example of
Monitoring
Information*

Master Agents

A master agent is a software program that provides the interface between an SNMP Network Manager and a subagent. Each workstation that includes a managed component needs to have a master agent. Each managed workstation can have a different master agent. A master agent performs the following tasks:

1. Parses requests from the SNMP Network Manager
2. Routes requests from the SNMP Network Manager to the subagents
3. Collects and formats responses from the subagents

4. Returns the responses to the SNMP Network Manager
5. Notifies the SNMP Network Manager when a request is invalid or information is unavailable

Subagents

A subagent is a software program that provides information to a master agent. Each managed component has a corresponding subagent. A subagent performs the following tasks:

1. Receives requests from the master agent
2. Collects the requested information
3. Returns the information to the master agent
4. Notifies the master agent when a request is invalid or information is unavailable

Managed Components

A managed component is hardware or software that provides a subagent. For example, database servers, operating systems, routers, and printers can be managed components if they provide subagents.

Event Notification

When an event occurs that affects the performance or availability of a managed component, the SNMP Network Manager can alert you to that condition. The following list describes some of the decisions that you can make about event notification:

- Define the conditions that should be monitored.
- Specify how frequently to poll for each condition.
When you determine the polling frequency, you must balance the need for prompt notification of an undesirable condition and the burden that polling puts on the network.
- Specify how the SNMP Network Manager notifies you of an event.
You might choose to have an icon blink or change colors when an event occurs.

Data Requests

A data request can be a one-time request or a periodic request. A one-time request is useful for comparing the data for two managed components. Periodic requests are useful for accumulating statistical information about a managed component.

Traps

You can configure the SNMP Network Manager to detect extraordinary events and notify you when they occur. The following list describes some of the decisions that you can make about traps:

- Define the conditions that should generate a trap.
- Specify how the SNMP Network Manager notifies you of a trap.
You might choose to have an icon blink or change colors when a trap occurs.
- Specify how the SNMP Network Manager responds to a trap.
The SNMP Network Manager can query the managed component to determine the cause and extent of the problem.

MIBs

A Management Information Base (MIB) is a group of tables that specify the information that a subagent provides to a master agent. MIBs follow SNMP protocols.

MIBs use a common interface definition language. The Structure of Management Information (SMI) defines this language and dictates how to use Abstract Syntax Notation One (ASN.1) to describe each table in the MIBs.

Naming Conventions


The name of each MIB table starts with the name of the MIB. Thus each table in the RDBMS MIB starts with **rdbms**. For example, the RDBMS MIB includes tables that are named **rdbmsSrvTable** and **rdbmsDbInfoTable**.

The name of each column in an MIB table starts with the name of the table, excluding **Table**. Thus, each column in **rdBmsSrvTable** starts with **rdBmsSrv**. For example, **rdBmsSrvVendorName** and **rdBmsSrvProductName** are columns in **rdBmsSrvTable**.

Hierarchy

All MIBs are part of an information hierarchy that the Internet Assigned Numbers Authority (IANA) defines. The hierarchy defines how to name tables and columns and how to derive the numerical object identifiers (OIDs). [Figure 1-6](#) shows the MIB hierarchy.

Figure 1-6
MIB Hierarchy



Even though you rarely see the full path to a table, column, or value, the path is important because the SNMP components use the numerical equivalent of the path to locate data. For example, the following value is the path to the Application MIB:

```
iso.org.dod.internet.mgmt.mib-2.application
```

An OID is the numerical equivalent of a path. It uniquely describes each piece of data that an SNMP Network Manager can obtain and is written as a string of numbers separated by periods (.). For example, the following value is the OID for the Application MIB:

1.3.6.1.2.1.27

The following value is the OID for a value in the Application MIB:

1.3.6.1.2.1.27.1.1.8.2

The first part of this OID is the OID for the Application MIB. The final part of the OID assigns values sequentially to each table in the MIB, each column in the table, and each value in a column.

IBM Informix Implementation of SNMP

In This Chapter	2-3
Purpose of IBM Informix SNMP	2-4
Event Notification	2-4
Data Requests	2-4
Traps	2-5
Information That OnSNMP Provides	2-6
SNMP Standard	2-7
SNMP Architecture.	2-7
IBM Informix SNMP Architecture on UNIX	2-7
IBM Informix SNMP Architecture on Windows.	2-9
Using SNMP on UNIX	2-11
The runsnmp.ksh Script.	2-12
UNIX Master Agents	2-13
Assuring Compatibility	2-13
Installing and Configuring a Master Agent Manually	2-14
Starting and Stopping a Master Agent	2-16
UNIX Subagent.	2-18
UNIX Server Discovery Process	2-18
Preparing onsrvapd Manually	2-19
Issuing the onsrvapd Command	2-19
Choosing an Installation Directory.	2-21
Using SNMP on Windows	2-21
Windows Master Agent	2-22
Windows Subagent	2-23
Starting and Stopping OnSNMP	2-23
Configuring OnSNMP	2-24

Windows Server Discovery Process	2-25
Starting and Stopping onsrvapd.	2-26
Installing the IBM Informix SNMP Agent	2-26
SNMP and Extended Parallel Server	2-27
GLS and SNMP	2-28
MIBs	2-29
Application MIB	2-29
RDBMS MIB	2-30
Informix Private MIB	2-31
Online MIB	2-32
XPS MIB	2-32
MIB Objects	2-32
Table Indexing	2-33
Numeric Index Values	2-33
Alphabetical Index Values	2-34
Refresh Control Value	2-35
Files Installed for SNMP	2-36
Files Installed on UNIX	2-36
Files Installed on Windows	2-37

In This Chapter

This chapter describes how SNMP manages Informix database servers. The IBM Informix implementation consists of the following components:

- Master agent
 - On UNIX, a master agent is provided through licensing agreements with vendors. See [“UNIX Master Agents” on page 2-13](#). ♦
 - On Windows, install the Microsoft SNMP Extendible master agent. ♦
- Subagent

The subagent for Informix database servers and coservers is OnSNMP.
- Managed components

In the IBM Informix implementation of SNMP, each database server and each coserver is a managed component.
- MIBs

OnSNMP uses several MIBs.

Only Extended Parallel Server provides coservers. ♦

Purpose of IBM Informix SNMP

The IBM Informix implementation of SNMP lets database administrators monitor Informix database servers, coservers, and databases.

Event Notification

You can configure an SNMP Network Manager to notify you when a specific event occurs. An event usually has a corresponding object in an MIB table. The following table describes four possible events and the MIB objects that correspond to them.

Event	MIB Object
A database server or coserver is not available.	onServerMode
Database availability changed.	rdbmsRelState
A chunk failed.	onChunkStatus
A table is running out of space.	onTablePagesAllocated onTablePagesUsed

For example, you might discover that an application that uses an Informix database server stopped responding. You can send email to the help desk to report this problem. The help desk can tell you about the problem, and you can look at **onSessionTable** to determine the cause of the problem.

Data Requests

You can issue a one-time data request to compare the configuration parameters of two database servers. You can issue periodic data requests to provide statistical information for assessing database performance or resource allocation.

For example, even if you use a database that is on a local host, you can call a remote technical support representative to report a problem. The problem might be that the data for the transactions running in a particular situation is less than expected. From the remote location, the technical support representative can query an SNMP Network Manager to determine the database server configuration, monitor the database server performance, and identify the bottleneck. OnSNMP provides this information to SNMP Network Managers through the master agent.

Traps

When the status of the database server changes from its current status to any status that is less available, OnSNMP sends a message to the SNMP Network Managers. For example, if a dbspace goes down, the database server status changes from full to limited availability. The message that OnSNMP sends is **rdbmsStateChange**, which is an unsolicited trap. When an SNMP Network Manager notifies you that it received an **rdbmsStateChange** trap, you can query the database server that generated the trap to determine the cause and extent of the problem.


For example, the logical logs for a database server might become full and cause the database server to become unavailable. OnSNMP can notice that the database server is unavailable and send an **rdbmsStateChange** trap to an SNMP Network Manager. The SNMP Network Manager can make an icon blink to notify you of the problem. You can then send data requests to determine the cause of the failure.

For information about traps and the EMANATE master agent, see [“Installing and Configuring a Master Agent Manually” on page 2-14](#).

Information That OnSNMP Provides

All the information that OnSNMP provides is available from other sources, such as the system catalog tables, the **sysmaster** and **sysutils** databases, dbaccess calls, and the **onstat** utility. However, the system catalog tables and the **onstat** utility refer only to a single database, and the **sysmaster** and **sysutils** databases refer only to a single database server or coserver. OnSNMP provides information that lets an SNMP Network Manager monitor all the Informix databases that are on a network. [Figure 2-1](#) illustrates this concept.

Figure 2-1
Monitoring Informix Databases



SNMP Standard

The SNMP standard has two versions: SNMPv1 and SNMPv2. The following table lists the versions of the SNMP standard with which OnSNMP complies.

Operating System	Version of the SNMP Standard
UNIX	SNMPv1 and SNMPv2
Windows	SNMPv1

SNMP Architecture


The architecture for the IBM Informix implementation of SNMP depends on your operating system.

UNIX

IBM Informix SNMP Architecture on UNIX

Figure 2-2 shows the SNMP architecture for Informix database servers on UNIX. Each managed workstation runs one master agent and one server discovery process. Each database server or coserver has one OnSNMP process.

Figure 2-2
IBM Informix SNMP Architecture on UNIX




Windows

IBM Informix SNMP Architecture on Windows

[Figure 2-3 on page 2-10](#) shows the SNMP architecture for Informix database servers on Windows. Each managed workstation runs one master agent. The master agent and the SNMP Network Manager use SNMP to communicate with each other. Each managed workstation runs one server discovery process and one **infxsnmp.dll**. One instance of the **onsnmp** subagent is started for each instance of Dynamic Server that runs on the managed workstation. OnSNMP and the master agent do not need to use SNMP to communicate with each other.

Figure 2-3
IBM Informix SNMP Architecture on Windows



UNIX

Using SNMP on UNIX

To use the IBM Informix implementation of SNMP, you must install and start the following software:

- **runsnmp.ksh**
- An SNMP Network Manager on a network management workstation
- A master agent on each workstation that includes an Informix database server or coserver
- An Informix database server or coserver

When you install an Informix database server or coserver, the installation procedure installs the OnSNMP subagent and the server discovery process as well as the files needed for SNMP support.


The discovery process discovers multiple server instances running on the host. These instances might belong to different versions that are installed on different directories. Whenever a server instance is brought online, the discovery process detects it and spawns an instance of OnSNMP to monitor the database server.

For information on how **runsnmp.ksh** automatically sets up and starts SNMP on UNIX, see [“The runsnmp.ksh Script” on page 2-12](#). The rest of this section describes how to do a manual setup and provides background information that you can use to diagnose setup problems.

The runsnmp.ksh Script

The **runsnmp.ksh** script on UNIX ensures that both the SNMP master agent and the **onsrvapd** server-discovery daemon are running on a host. The **runsnmp.ksh** file is in the **\$INFORMIXDIR/snmp** directory. You must correctly set the **INFORMIXDIR** environment variable to the latest installed version of the product and run the script as **root**.

Issue the **runsnmp.ksh** commands that the following diagram shows.



Option	Description
-m <i>master_agent_args</i>	The master-agent arguments can be either stop or valid master-agent arguments.
-s <i>server_disc_args</i>	The server-discovery arguments can be either stop or valid onsrvapd arguments.
start	Starts snmpdm or snmpdp and onsrvapd if they are not running. This option is the default.
stop	Stops snmpdm or snmpdp and onsrvapd if they are already running and exits.

The *master_agent_args* and the *server_disc_args* are not checked for correctness.

The following examples illustrate how to use **runsnmp.ksh**:

- Start **snmpdm** or **snmpdp** and **onsrvapd** if they are not running.
`runsnmp.ksh`
- Stop **onsrvapd** and **subagents** and then exit.
`runsnmp.ksh -s stop`

- Stop **onsrvapd** and any **subagents** and then restart **onsrvapd**.

```
runsnmp.ksh -s stop start
```
- Stop **snmpdm** or **snmpdp**, **onsrvapd**, and any **subagents** and then exit.

```
runsnmp.ksh stop
```
- Stop **snmpdm** or **snmpdp**, **onsrvapd**, and any **subagents** and then restart **snmpdm** or **snmpdp** and **onsrvapd**.

```
runsnmp.ksh stop start
```
- Start **snmpdm** or **snmpdp**, if it is not running, and then start **onsrvapd** with the **none** option, if it is not running.

```
runsnmp.ksh -s "-none"
```

UNIX Master Agents

On UNIX, master agents are provided through licensing agreements. The following table lists these master agents.

Master Agent	Company	Web Site Home Page
EMANATE, Version 14.2	SNMP Research	www.snmp.com
Patrol, Version 2.3	BMC Software	www.bmc.com

For some UNIX platforms, you might be able to use a master agent other than the one provided with the database server. To see whether this applies to your platform, see your release notes.

Assuring Compatibility

The following guidelines assure master agent compatibility:

- Only one master agent is provided, usually EMANATE or Patrol, for each UNIX platform type.
- The subagent that works with the master agent is also provided with the database server.

- In some cases, the platform vendor also supplies a master agent that works with the subagent provided with the database server. This is generally true only if the platform vendor supplies the same type of master agent as that provided with the database server and if the version number of the vendor-supplied master agent is greater than or equal to that of the version provided with the database server.
- You should run only one instance of a master agent on a platform. You can run multiple instances of subagents, including multiple instances of **onsnmp**, if multiple database server or coserver instances exist.
- Informix subagents can coexist with subagents that platform or third-party vendors supply if all the subagents share a common, compatible master agent.

Installing and Configuring a Master Agent Manually

The **runsnmp.ksh** script automatically performs the steps in this section for the master agents provided with the database server. If you bought a master agent from another vendor, follow the installation instructions that the vendor provides.

To configure the EMANATE master agent

1. Set the following environment variables:
 - Make sure that the **PATH** environment variable includes **\$INFORMIXDIR/bin**.
 - Set **SR_AGT_CONF_DIR** to the directory for the EMANATE configuration file.
 - Set **SR_LOG_DIR** to the directory for the EMANATE log file.

The EMANATE configuration files are located in the **\$INFORMIXDIR/snmp/snmp** directory. The log files are located in the **/tmp** directory. The **/tmp** directory is the default location if the variable is not set.

2. Make sure that either the Network Information Services or the **/etc/services** file configures UDP ports 161 and 162 as the SNMP ports.
 - a. Use the **grep** command to search **/etc/services** for **snmp**. The output from **grep** should be similar to the following lines:


```
snmp      161/udp
snmp-trap162/udp
```
 - b. Make sure that UDP port 161 is available so that the master agent can be the owner of the port.

To configure the Patrol master agent

1. Make sure that the **PATH** environment variable includes **\$INFORMIXDIR/bin**.
2. Make sure that either the Network Information Services or the **/etc/services** file configures UDP ports 161 and 162 as the SNMP ports and port 199 as the SMUX port.
 - a. Use the **grep** command to search **/etc/services** for **snmp** and **smux**. The output from **grep** should be similar to the following lines:


```
snmp      161/udp
snmp-trap162/udp
smux      199
```
 - b. Make sure that UDP port 161 is available so that the master agent can be the owner of the port.
3. If necessary, modify the configuration parameters.
 The Patrol configuration file is located in the **\$INFORMIXDIR/snmp/peer** directory. For information about the Patrol configuration values, see the BMC Software Web site, which is listed in [“UNIX Master Agents” on page 2-13](#). The Patrol log files are located in the **/tmp** directory.

Starting and Stopping a Master Agent

Start the master agent before you start an Informix database server or coserver, and stop all Informix database servers and coservers on a workstation before you stop the master agent.

The best way to start a master agent is to run the **runsnmp.ksh** script as part of the startup procedure for the system. Similarly, the best way to stop a master agent is to run the **runsnmp.ksh** script as part of the shutdown procedure. However, you can start or stop a master agent manually if you prefer. Additionally, while a master agent is running, you can make sure that it is running correctly.

If you bought a master agent from another vendor, follow the instructions that the vendor provides.

Starting and Stopping a Master Agent Automatically

The **runsnmp.ksh** script automatically starts the EMANATE or Patrol master agent at startup and stops it at shutdown.

Starting and Stopping a Master Agent Manually

This section describes how to start or stop a master agent if you do not use the **runsnmp.ksh** script.

To start a master agent manually

1. Log in as **root**.

If you do not have **root** user privileges, ask your system administrator to start the master agent.

2. Stop or kill any master agents and daemons that are running on the workstation.
3. Enter the following command:

For EMANATE:

```
snmpdm &
```

For Patrol:

```
snmpdp $INFORMIXDIR/snmp/peer/CONFIG NOV &
```


To stop a master agent manually

1. Log in as **root**.
If you do not have **root** user privileges, ask your system administrator to stop the master agent.
2. Kill the following process:
For EMANATE, **snmpdm**
For Patrol, **snmpdp**

The following table describes the command-line options that you can include in the `snmpdm` command for the EMANATE master agent.

Option	Description
-apall	Turn on all messages.
-aperror	Turn on error messages. Error messages are already turned on by default.
-aptrace	Turn on trace messages.
-apwarn	Turn on warning messages. Warning messages are already turned on by default.
-d	Run the master agent in the foreground.

To make sure that a master agent is running correctly

1. Check the master agent log file to verify that the master agent has not generated any errors. The log file is located in the **/tmp** directory unless the environment variable mentioned in [“To configure the EMANATE master agent” on page 2-14](#) is set to a different directory.
2. Verify that the process is running:
For EMANATE, **snmpdm**
For Patrol, **snmpdp**

UNIX Subagent

When you install an Informix database server or coserver on UNIX, the installation procedure installs OnSNMP. OnSNMP consists of the **onsnmp** program.

Under normal circumstances, you do not need to start or stop OnSNMP explicitly. If you experience abnormal circumstances and need to start or stop OnSNMP explicitly, contact Technical Support. For contact information, refer to your *Installation Guide*.

The following additional files are provide with the database server for SNMP support.

Program	Description
onsrvapd daemon	When you start an Informix database server or coserver that is on this workstation, onsrvapd detects this event and starts OnSNMP for the database server or coserver. When the database server or coserver halts, onsrvapd stops OnSNMP for that database server or coserver. See “UNIX Server Discovery Process” on page 2-18 .
runsnmp.ksh script	This script starts onsrvapd . It also starts the master agent that is appropriate for the platform. If you want to run OnSNMP, you need to run runsnmp.ksh each time that you reboot. See “The runsnmp.ksh Script” on page 2-12 .

UNIX Server Discovery Process

The **runsnmp.ksh** script automatically starts the UNIX server discovery process, as [“The runsnmp.ksh Script” on page 2-12](#) describes. This section provides procedures for working manually with **onsrvapd**. Some of these procedures include instructions on how to configure OnSNMP.

The principles for starting and stopping **onsrvapd** manually are the same as those for a master agent: start **onsrvapd** before you start an Informix database server or coserver, and stop all Informix database servers and coservers on a workstation before you stop **onsrvapd**.

Preparing onsrvapd Manually

If you do not use **runsnmp.ksh** to automatically prepare and start **onsrvapd**, perform the steps in this section.


To prepare onsrvapd

- 1. Make sure that the owner of **onsrvapd** is **root** and that the group is **informix**.
- 2. Make sure that the setuid (sticky) bit is set for the **onsrvapd** file.

Issuing the onsrvapd Command

You can specify the **onsrvapd** command-line options that [Figure 2-4](#) shows. Some of these options affect OnSNMP.

Figure 2-4
onsrvapd Command



Option	Description
-d	Flag that tells UNIX to run onsrvapd once and terminate it instead of starting it as a daemon.
-g <i>logginglevel</i>	Logging level to which OnSNMP logs debug information. Valid values are 2, 4, 8, 16, 32, and 64. The default value is 32. The lower the value, the higher the amount of logging. The onsrvapd daemon passes this value to OnSNMP.
-k <i>lingermnts</i>	Number of minutes that onsrvapd waits after a database server or coserver goes down before onsrvapd kills the corresponding OnSNMP. If <i>lingermnts</i> is 0, onsrvapd waits indefinitely.
-l <i>pathname</i>	Directory for the error log files. The filename of the OnSNMP error log is onsnmp.servername.log . For example, if your server name is MyServer, the filename of the OnSNMP error log is onsnmp.MyServer.log . The filename of the onsrvapd error log is onsrvapd.log .
-p <i>pollsecs</i>	Frequency, in seconds, with which OnSNMP polls the database server or coserver. The default value is 5 seconds. The onsrvapd daemon passes this value to OnSNMP.
-r <i>level</i>	Refresh control value. For a description, see “Refresh Control Value” on page 2-35 .
-V	Prints the OnSNMP version number.

To start onsrvapd manually

1. Stop or kill any daemons that are running on the workstation.
2. Enter the following command:

`onsrvapd`

To stop **onsrvapd** manually, kill the **onsrvapd** process.

To make sure that onsrvapd is running correctly

1. Check the log file to verify that **onsrvapd** has not generated any errors. The log file is located in the `/tmp` directory.
2. Verify that **onsrvapd** is running.

Choosing an Installation Directory

When you have multiple Informix installation directories on a host computer, you must set the latest installation directory as **INFORMIXDIR** before you run the **runsnmp.ksh** script to start OnSNMP. If all the directories are for the same type of database server, use the installation directory that has the latest database server version number.

One way to determine the latest directory to use with different types of database server lines is to find the latest version of the SNMP master agent.

- The EMANATE master agent displays the version when you run it.
- The BMC Patrol agent also displays a version number.

Windows

Using SNMP on Windows

To use the IBM Informix implementation of SNMP, you must install and start the following software:

- Microsoft's SNMP service on each workstation that includes an Informix database server or coserver
- An Informix database server or coserver

When you install an Informix database server or coserver, the installation procedure installs the OnSNMP subagent and the server discovery process as well as the files needed for SNMP support.

Windows Master Agent

The Microsoft TCP/IP custom installation procedure installs the Microsoft SNMP Extendible master agent. For information about this master agent, see the Microsoft TCP/IP Help.

To start the Microsoft TCP/IP Help

1. Choose **Start→Help**.
2. Choose the **Index** tab.
3. Enter the following phrase in the text box:

SNMP

In response to this search request, the help system displays a **Topics Found** dialog box.

4. Choose **TCP/IP Procedures Help**.

Important: To start or stop the Microsoft SNMP Extendible master agent, you must be a member of the **Administrator Group** on the host workstation.



Windows Subagent

On Windows, OnSNMP comprises the following files. The table also lists the directories in which the IBM Informix installation procedure installs each file.

File	Description	Directory
infxsnmp.dll	Library that provides the interface between onsnmp.exe and the master agent. The IBM Informix installation procedure installs one infxsnmp.dll on each workstation. The initialization process for the master agent loads infxsnmp.dll .	%Windows%\system32
onsnmp.exe	Subagent program. The IBM Informix installation procedure installs an onsnmp.exe file for each database server or coserver.	%INFORMIXDIR%\bin
onsrvapd.exe	Server discovery process, which starts onsnmp.exe for each database server or coserver that starts. The IBM Informix installation procedure performs the following tasks for onsrvapd.exe : <ul style="list-style-type: none"> ■ Installs one onsrvapd.exe on each workstation ■ Creates the Informix Server Discovery Process for SNMP in the control panel and configures it to start automatically when the system reboots 	%Windows%\system32

When you install an Informix database server or coserver, the installation procedure automatically installs OnSNMP. When you start an Informix database server or coserver that is on a network that uses SNMP, **onsrvapd.exe** detects this event and starts OnSNMP for the database server or coserver. When the database server or coserver halts, **onsrvapd.exe** stops OnSNMP for that database server or coserver.

Starting and Stopping OnSNMP

Under normal circumstances, you do not need to start or stop OnSNMP explicitly. If you are experiencing abnormal circumstances and need to start or stop OnSNMP explicitly, contact Technical Support. For contact information, refer to your *Installation Guide*.

Configuring OnSNMP

The Informix installation procedure creates a new registry key, **OnSnmSubagent**, under **HKEY_LOCAL_MACHINE\SOFTWARE\Informix**.

The following table describes the **OnSnmSubagent** arguments that you can change.

Argument	Value	Description
Environment\ LINGER_TIME	<i>lingermts</i>	Number of minutes that the master agent waits after a database server or coserver goes down before the master agent kills the corresponding OnSNMP. If <i>lingermts</i> is 0, the master agent waits indefinitely.
Environment\ LOGDIR	<i>pathname</i>	Complete path of the OnSNMP error-log file, including filename
Environment\ REFRESH_TIME	<i>pollsecs</i>	Frequency, in seconds, with which OnSNMP polls the database server or coserver
Environment LOGLEVEL	<i>loglevel</i>	Logging level to which OnSNMP logs debugging information. The default value is 3. The onsrvapd daemon passes this value to OnSNMP.

The following table describes the **OnSnmSubagent** arguments that you should not change.

Argument	Value	Description
Pathname	pathname	Complete path of infxsnmp.dll, including filename
MIBS\APPLMIB	apploid	OID for the Application MIB
MIBS\ONMIB	onoid	OID for the Online MIB
MIBS\RDBMSMIB	rdbmsoid	OID for the RDBMS MIB
MIBS\XPSMIB (For XPS only)	xpsoid	OID for the XPS MIB

The Informix installation procedure also creates a new argument, **INFXSMP**, under **HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Services\SNMP\Parameters\ExtensionAgents**. This new argument specifies the location of the **OnSnmpSubagent** registry key, including the name of the key.

To change the OnSNMP configuration, change the values for these arguments.

Windows Server Discovery Process

The Informix Server Discovery Process for SNMP is known as **onsrvapd**. It is installed as a Windows service that runs under the Informix user. The discovery process discovers multiple server instances running on the host. These instances might belong to different versions that are installed on different directories. Whenever a server instance is brought online, the discovery process detects it and spawns an instance of OnSNMP to monitor the database server.

Starting and Stopping onsrvapd

You can start **onsrvapd** from the services folder in the control panel or from a command prompt. To start and stop **onsrvapd** from a command prompt, enter the following commands:

- To start **onsrvapd**, enter:

```
net start onsrvapd
```

- To stop **onsrvapd**, enter:

```
net stop onsrvapd
```

The OnSNMP Discovery Process (onsrvapd.exe) is installed as an Windows service and starts and stops automatically. You do not need to issue commands at the command line. In the event you want to issue commands from the command line, see the command-line syntax listed in [“Issuing the onsrvapd Command” on page 19](#).

To make sure that onsrvapd is running correctly

1. Check the log file to verify that **onsrvapd** has not generated any errors. For location of the log files, see your release notes.
2. Verify that **onsrvapd** is running.

Installing the IBM Informix SNMP Agent

If you install the Microsoft SNMP Extendible master agent after you install the Informix database server or coserver, the Informix installation procedure cannot create INFXSMP. To correct this problem, run a program called **inssnmp** to complete the OnSNMP installation.

To run inssnmp

1. Start a Command Prompt session.
2. Go to %INFORMIXDIR%\bin.
3. Enter the following command:

```
inssnmp
```

Tip: *If you install a Windows service pack on your computer before you install the Microsoft SNMP Extendible master agent, you might need to reinstall the service pack.*



SNMP and Extended Parallel Server

For Extended Parallel Server, the MIB objects that OnSNMP supports depend on whether or not it is running on coserver 1.

Coserver 1 supports the following tables:

- Application (all MIB objects)
- RDBMS (all MIB objects)
- Online (all MIB objects except Enterprise Replication objects)
- XPS (all MIB objects)

All other coservers support the following tables:

- Application (all MIB objects)
- RDBMS
 - **rdbmsSrvInfoTable**
 - **rdbmsSrvLimitedResourceTable**
 - **rdbmsSrvParamTable**
 - **rdbmsSrvTable**
 - **rdbmsTraps**
- Online
 - **onActiveBarTable**
 - **onChunkTable**
 - **onDbospaceTable**
 - **onLockTable**
 - **onLogicalLogTable**
 - **onPhysicalLogTable**
 - **onServerTable**
 - **onSessionTable**
 - **onSqlHostTable**
 - **onXpsTable**

These tables and MIB objects are described in [Chapter 3, “MIB Reference.”](#)

The **onXpsTable** MIB table specifies which OnSNMP instance is the subagent on coserver 1 for Extended Parallel Server. The subagent responds to SNMP requests for XPS MIB information about the entire database server as well as about coserver 1.

GLS and SNMP

IBM Informix products include a Global Language Support (GLS) feature, which lets you work with languages that use code sets other than the standard English code set. However, the SNMP protocols that OnSNMP supports (SNMPv1 and SNMPv2) do not recognize these different code sets.

OnSNMP uses the U.S. English locale when it sends information to the master agent. If OnSNMP cannot convert the code set of the database to the U.S. English locale, it fails and returns error -23101 with the following message:

```
Unable to load locale categories.
```

OnSNMP sends only 7-bit characters. If an eighth bit is present, OnSNMP truncates it. Thus, when an SNMP Network Manager requests character information, OnSNMP returns a value. However, the value might not reflect the name of the database or table.

OnSNMP sends numeric information correctly, regardless of the code set that the database uses.

MIBs

This section describes the types of MIBs and the types of MIB objects that the Informix database server uses. For a description of MIBs, see [page 1-9](#).

OnSNMP uses the following MIBs:

- Application MIB
- Relational Database Management System (RDBMS) MIB
- Informix Private MIB
- Online MIB in the Informix Private MIB
- XPS MIB in the Informix Private MIB ♦

Application MIB

The Application MIB is a public MIB, which means that the Internet Engineering Task Force (IETF) specifies the structure of the MIB and the MIB tables. A public MIB is the same for all managed components on an SNMP network, not just for IBM Informix products. OnSNMP uses only **applTable**, which is the portion of the Application MIB that the RDBMS MIB requires. [Figure 1-6 on page 1-10](#) shows the position of the Application MIB in the MIB hierarchy.

The following value is the path to the Application MIB:

```
iso.org.dod.internet.mgmt.mib-2.application
```

The following value is the OID for the Application MIB:

```
1.3.6.1.2.1.27
```

RDBMS MIB

The RDBMS MIB is a public MIB, which means that the IETF specifies the structure of the MIB and the MIB tables. A public MIB is the same for all managed database components. However, some of the definitions in the RDBMS MIB are purposely vague to let each vendor tailor the entries to a specific database server. For example, **rdbmsSrvLimitedResourceTable** contains information about the resources that a database server uses. Each database server vendor can decide which resources to include in this table. [Figure 1-6 on page 1-10](#) shows the position of the RDBMS MIB in the MIB hierarchy.

The following value is the path to the RDBMS MIB:

```
iso.org.dod.internet.mgmt.mib-2.rdbmsMIB
```

The following value is the OID for the RDBMS MIB:

```
1.3.6.1.2.1.39
```

Informix Private MIB

The Informix Private MIB is a private MIB, which means that a private enterprise defines and uses it. The Internet Assigned Numbers Authority (IANA) assigns a unique enterprise identifier to each company that uses the SNMP protocol. The Informix Private MIB describes information that is relevant to the specific architecture and features of Informix database servers, coservers, and databases. [Figure 2-5](#) shows the MIB hierarchy for the Informix Private MIB.




Figure 2-5
MIB Hierarchy for
the Informix Private
MIB

The following value is the path to the Informix Private MIB:

```
iso.org.dod.internet.private.enterprises.informix
```

The following value is the OID for the Informix Private MIB:

```
1.3.6.1.4.1.893
```

Online MIB

The Online MIB is in the Informix Private MIB. The Online MIB contains information for all Informix database servers and coservers. In the Online MIB, all tables are below the following node:

```
servers.onlineMIB.onlineObjects
```

The OID for each table in the Online MIB starts with the following value:

```
1.3.6.1.4.1.893.1.1.1
```

XPS MIB

The XPS MIB is in the Informix Private MIB. The XPS MIB contains information for database servers and coservers on Extended Parallel Server. In the XPS MIB, all tables are below the following node:

```
servers.xpsMIB.xpsObjects
```

The OID for each table in the XPS MIB starts with the following value:

```
1.3.6.1.4.1.893.1.3.1
```

MIB Objects

An MIB object is similar to a column in a table. The IBM Informix implementation of SNMP recognizes the following types of MIB objects:

- Traps are defined as MIB objects, but they cannot be retrieved. Instead, when a certain condition is detected, OnSNMP issues an event that includes the object ID that the trap defines.
- Catalog-based MIB objects exist only if the refresh control value (described on [page 2-35](#)) is `once` or `all`.
- Catalog-based MIB objects exist only if the refresh control value is `once` or `all` and they are only on coserver 1.
- XPS-only MIB objects exist only on the node that hosts coserver 1 for Extended Parallel Server. ♦
- Enterprise Replication objects are tables that exist only if a database server is configured to participate in Enterprise Replication.

XPS

XPS

Table Indexing

In the description of the MIBs in [Chapter 3](#), the header for each table specifies how each row in the table is indexed. A table can have one or more indexes. For example, the header for **rdBmsSrvTable** is **rdBmsSrvTable[applIndex]**, which means that the table has one index called **applIndex**.

Each index value is concatenated to the column OID with periods between each value. If a MIB table has several indexes, the indexes are concatenated one after the other. Most SNMP Network Managers display only the final portion of the OID that relates to the table being displayed. Some SNMP Network Managers display the OID as part of the information about each individual item; other SNMP Network Managers display the OID as part of a header for a list of values.

Numeric Index Values

The following line is an example of indexed information:

```
rdBmsRelActiveTime.72000003.893072000 = 11/16/98 12:34:08
```

The following table describes how to interpret the example. For more information about these values, see “[rdBmsRelTable](#)” on [page 3-10](#).

Index Subvalue	Description
rdBmsRelActiveTime	Name of the column
72000003	rdBmsDbIndex
893072000	applIndex

Alphabetical Index Values

When an index is an alphabetical string, such as the name of a configuration parameter, the OID for that index consists of the following elements, all separated by periods:

- Number of letters in the name
- ASCII value for each letter

The following line is an example of alphabetical indexed information:

```
rdbmsSrvParamCurrValue.893072000.4.76.82.85.83.1 = 8
```

The following table describes how to interpret this example. For more information about these values, see [“rdbmsSrvParamTable” on page 3-14](#).

Index Subvalue	Description
rdbmsSrvParamCurrValue	Name of the column
893072000	applIndex
4.76.82.85.83	rdbmsSrvParamName: 4 = Number of letters 76 = L 82 = R 85 = U 83 = S
1	rdbmsSrvParamSubIndex

Refresh Control Value

As a background task, OnSNMP periodically updates the contents of MIB tables that it derives from catalog information. The refresh control value determines the amount of time that OnSNMP spends refreshing these MIB tables versus the amount of time that it spends responding to queries from the master agent.

Specify the refresh control value with the **runsnmp.ksh -s -r** command-line option or the **onsrvapd -r** command-line option. The following table lists the MIB tables that this value affects. See also [“Issuing the onsrvapd Command” on page 2-19](#).

Database-Related MIB Tables	Table-Related MIB Tables
rdbmsDbInfoTable	onActiveTableTable
rdbmsDbTable	onFragmentTable
rdbmsRelTable	onTableTable
onBarTable	
onDatabaseTable	

The following table describes the possible values for the refresh control value.

Value	Description
a or all	Refresh the database-related and table-related tables periodically.
n or none	Do not fill or refresh any of the catalog-based tables. Instead, leave the catalog-based tables empty.
o or once	Fill the database-related and table-related tables once at startup.

The following table lists the default refresh control value for each operating system.

Operating System	Default Refresh Control Value
UNIX	once
Windows	all

The best value to use depends on the environment and how you use OnSNMP. If the list of tables and databases changes frequently, it is probably best to use a value of `all` to make sure that the MIB tables are accurate. If the environment includes many tables and databases, it is probably best to use a value of `once` to let OnSNMP respond to queries.

Files Installed for SNMP

This section lists the files that are typically installed for the IBM Informix implementation of SNMP on UNIX and Windows.

UNIX

Files Installed on UNIX

The `runsnmp.ksh` file exists for all UNIX versions of SNMP support.

The following files are installed in `$INFORMIXDIR/bin`.

Filename	Description
<code>onsnmp</code>	OnSNMP executable
<code>onsrvapd</code>	Server discovery process
<code>snmpdm</code>	EMANATE executable or a dummy file for UNIX platforms that EMANATE does not support
<code>snmpdp</code>	Patrol executable or a dummy file for UNIX platforms that Patrol does not support

The following files are installed in `$INFORMIXDIR/snmp`.

Filename	Description
Files for the MIBs:	
<code>./snmpr/snmpd.cnf</code>	EMANATE configuration file or a dummy file for UNIX platforms that EMANATE does not support
<code>./peer/CONFIG</code>	Patrol configuration file or a dummy file for UNIX platforms that Patrol does not support
<code>.runsnmp.ksh</code>	Script that starts the master agent and onsrvapd

OnSNMP uses the following log files by default.

Filename	Description
<code>snmp.log</code>	Log file for EMANATE; not installed on UNIX platforms that EMANATE does not support
<code>onsrvapd.log</code>	Log file for onsrvapd .
<code>onsnmp.*.log</code>	Log file for onsnmp .
For Extended Parallel Server, the path is onsnmp.servername.coserver#.log	
The <i>coserver#</i> is optional.	
For Dynamic Server, the path is onsnmp.servername.log	

Windows

Files Installed on Windows

The following files are created in `%Windows%\system32`.

Filename	Description
<code>infxsnmp.dll</code>	DLL for OnSNMP
<code>onsrvapd.exe</code>	Server discovery process

The following file is created in %INFORMIXDIR%\bin.

Filename	Description
onsnmp.exe	OnSNMP executable

In addition, log files are created in the directories that are specified in the registry.

MIB Reference

In This Chapter	3-3
Application MIB.	3-6
RDBMS MIB	3-8
rdbmsDbInfoTable.	3-8
rdbmsDbLimitedResourceTable	3-9
rdbmsDbParamTable.	3-9
rdbmsDbTable	3-9
rdbmsRelTable	3-10
rdbmsSrvInfoTable	3-11
rdbmsSrvLimitedResourceTable	3-13
rdbmsSrvParamTable.	3-14
rdbmsSrvTable	3-15
rdbmsTraps	3-16
Online MIB in the Informix Private MIB	3-17
onActiveBarTable	3-17
onActiveTableTable	3-18
onBarTable	3-20
onChunkTable	3-21
onDatabaseTable	3-23
onDbospaceTable	3-24
onErQueueTable	3-26
onErSiteTable	3-27
onFragmentTable	3-29
onLockTable.	3-31
onLogicalLogTable	3-32
onPhysicalLogTable	3-33

onServerTable	3-34
onSessionTable	3-37
onSqlHostTable	3-40
onTableTable	3-41
onXpsTable	3-44
XPS MIB in the Informix Private MIB.	3-45
xpsCogroupMemberTable	3-45
xpsCogroupTable	3-45
xpsCoserverTable	3-46
xpsDbsliceDbospaceTable.	3-47
xpsDbsliceTable.	3-48

In This Chapter

This chapter describes the MIBs that OnSNMP uses. An SNMP Network Manager hides most of the structure of the MIBs. However, an understanding of this structure can help you comprehend the information that an SNMP Network Manager displays.

The descriptions in this chapter are brief. For detailed descriptions, see the online MIB files. The following table lists the directories for the MIB files.

Operating System	MIB Directory
UNIX	\$INFORMIXDIR/snmp
Windows	%INFORMIXDIR%\etc

Many MIB values are for database servers or coservers, depending on the types of database servers that you are using.

Only Extended Parallel Server provides coservers. ♦

This chapter presents the MIB tables in alphabetical order. For the logical order, see the MIB files. The following table summarizes the MIB tables that OnSNMP uses and indicates the page that contains more information.

XPS

MIB	Table	Description
Application (See page 3-6)	applTable	Attributes for each database server or coserver
RDBMS (See page 3-8)	rdbmsDbInfoTable	Information about databases
	rdbmsDbTable	Information about databases

(1 of 3)

MIB	Table	Description
Online (See page 3-17)	rdbmsRelTable	Information about the relationship between a database and the database server or coserver with which it is associated
	rdbmsSrvInfoTable	Information about the database server or coserver since it was started
	rdbmsSrvLimited-ResourceTable	Information about the limited resources for each database server or coserver
	rdbmsSrvParamTable	Information about the configuration parameters for each database server or coserver
	rdbmsSrvTable	Information about a database server or coserver
	rdbmsTraps	Information about the traps that OnSNMP can send to the SNMP Network Manager
	onActiveBarTable	Information about the current ON-Bar activity
	onActiveTableTable	Information about the open and active database tables
	onBarTable	Information about the backup and restore history
	onChunkTable	Information about the chunks that the database servers and coservers use
	onDatabaseTable	Information about active databases
	onDbospaceTable	Information about dbspaces
	onErQueueTable	Information about the Enterprise Replication queue
	onErSiteTable	Information about the Enterprise Replication site
	onFragmentTable	Information about the fragments that are in fragmented database tables
	onLockTable	Information about the active locks that database servers and coservers are using
	onLogicalLogTable	Information about logical logs
	onPhysicalLogTable	Information about physical logs

(2 of 3)

MIB	Table	Description
	onServerTable	Status and profile information about each active database server and coserver
	onSessionTable	Information about each session
	onSqlHostTable	Copy of the connection information
	onTableTable	Information about a database table
	onXpsTable	Indicates the OnSNMP instance that is the subagent for Extended Parallel Server
XPS (See page 3-45)	xpsCogroupMemberTable	Information about coservers as members of cgroups
	xpsCogroupTable	Information about cgroups as members of database servers
	xpsCoserverTable	Information about coservers as members of database servers
	xpsDbsliceDbpaceTable	Information about each dbspace that is in a database server
	xpsDbsliceTable	Information about each dbslice that is in a coserver

(3 of 3)

Application MIB

Informix uses one table from the application MIB. This table provides general-purpose attributes for each database server or coserver.

applTable

The following list summarizes this table:

- Contents:
- Attributes for each database server or coserver
- Index:
- applIndex
- Scope of a row:
- One database server or coserver

The table has the following MIB objects.

MIB Object	Description
applIndex	<div>Unique integer index that identifies each database server or coserver. This value is the sum of the following values:</div> <div><div>■ Informix Enterprise ID * 1,000,000</div><div>The Informix Enterprise ID is 893. Therefore, Enterprise ID * 1,000,000 is 893,000,000.</div><div>■ SERVERNUM * 1000</div><div>■ Coserver ID for Extended Parallel Server or 0 for any other type of database server</div></div>
applName	Name of the database server or coserver
applDirectoryName	No OnSNMP support for this MIB object
applVersion	Version of the database server or coserver
applUptime	<div>Time when the database server or coserver was last initialized</div> <div>This time is the system time according to the master agent. If the database server or coserver was last initialized before OnSNMP was last initialized, this value is 0.</div>

MIB Object	Description
applOperStatus	<p>Operating status of the database server or coserver:</p> <ul style="list-style-type: none"> ■ up (1) ■ down (2) ■ halted (3) ■ -- (4): OnSNMP does not use this value. ■ restarting (5)
applLastChange	<p>Time when the database server or coserver entered its current state</p> <p>This time is the system time according to the master agent. If the database server or coserver was last initialized before OnSNMP was last initialized, this value is 0.</p>
applInboundAssociations	Number of current SQLCONNECT actions
applOutboundAssociations	OnSNMP does not support this MIB object.
applAccumulatedInboundAssociations	Number of SQLCONNECT actions that have occurred so far
applAccumulatedOutboundAssociations	OnSNMP does not support this MIB object.
applLastInboundActivity	<p>Time for the most recent attempt to start or stop a session with a database server or coserver</p> <p>This time is the system time according to the master agent.</p>
applLastOutboundActivity	OnSNMP does not support this MIB object.
applRejectedInboundAssociations	Number of times that the database server or coserver rejected an input connection due to administrative reasons or resource limitations
applFailedOutboundAssociations	OnSNMP does not support this MIB object.

(2 of 2)

RDBMS MIB

The RDBMS MIB defines several tables that provide information about managed database servers or coservers and their databases.

rdbmsDbInfoTable

The following list summarizes this table:

- Contents:Information about databases
- Index:**rdbmsDbIndex**
- Scope of a row:One database that does not have an access state of **unavailable**

(The **rdbmsRelState** value indicates the access state for the database.)

The table has the following MIB objects.

MIB Object	Description
rdbmsDbIndex	See “ rdbmsDbTable ” on page 3-9.
rdbmsDbInfoProductName	Name of the database product. For example, this value might be Dynamic Server.
rdbmsDbInfoVersion	Version number of the database server or coserver that created or last restructured this database
rdbmsDbInfoSizeUnits	Units for rdbmsDbInfoSizeAllocated and rdbmsDbInfoSizeUsed : <ul style="list-style-type: none">■ Bytes (1)■ Kilobytes (2)■ Megabytes (3)■ Gigabytes (4)■ Terabytes (5)

MIB Object	Description
rdbmsDbInfoSizeAllocated	Estimated size allocated for this database in the units that rdbmsDbInfoSizeUnits specifies
rdbmsDbInfoSizeUsed	Estimated size in use for this database in the units that rdbmsDbInfoSizeUnits specifies
rdbmsDbInfoLastBackup	Date and time when the latest backup of the database was performed. If the database has never been backed up, this value is <code>noSuchInstance</code> (SNMPv2) or <code>noSuchName</code> (SNMPv1).

(2 of 2)

rdbmsDbLimitedResourceTable

OnSNMP does not support this table.

rdbmsDbParamTable

OnSNMP does not support this table.

rdbmsDbTable

The following list summarizes this table:

- Contents: Information about databases
- Index: **rdbmsDbIndex**
- Scope of a row: One database

The table has the following MIB objects.

MIB Object	Description
rdbmsDbIndex	Unique integer index that identifies a database. This value is the sum of the following values: <ul style="list-style-type: none">■ $\text{SERVERNUM} * 1,000,000$■ If SERVERNUM is 0, OnSNMP uses 256 instead of 0.■ Database number
rdbmsDbPrivateMibOID	OID for the Informix Private MIB: 1.3.6.1.4.1.893
rdbmsDbVendorName	Name of the database vendor: Informix Software, Inc.
rdbmsDbName	Name of the database
rdbmsDbContact	Login name of the person who created the database

rdbmsRelTable

The following list summarizes this table:

Contents:	Information about the relationship between a database and the database server or coserver with which it is associated
Index:	rdbmsDbIndex, applIndex
Scope of a row:	One database One database coserver pair. ♦

XPS

The table has the following MIB objects.

MIB Object	Description
rdbmsDbIndex	See “rdbmsDbTable” on page 3-9.
applIndex	See “applTable” on page 3-6.
rdbmsRelState	Access state between the database server or coserver and the database: <ul style="list-style-type: none">■ Other (1): The database server or coserver is online, but one of the dbspaces of the database is down.■ Active (2): The database server or coserver is actively using the database. The database server or coserver is online, and a user opened the database.■ Available (3): The database server or coserver could use the database if asked to do so. The database server or coserver is online, but the database is not open.■ Restricted (4): The database is not completely available. The database server or coserver is online, and a user opened the database in exclusive mode.■ Unavailable (5)
rdbmsRelActiveTime	Date and time that the database server or coserver made the database active. If rdbmsRelState is not active, this value is noSuchInstance (SNMPv2) or noSuchName (SNMPv1).

rdbmsSrvInfoTable

The following list summarizes this table:

Contents:	Information about the database server or coserver since it was started
Index:	applIndex
Scope of a row:	One database server or coserver

The table has the following MIB objects.

MIB Object	Description
applIndex	See “ applTable ” on page 3-6.
rdbmsSrvInfoStartupTime	Date and time when the database server or coserver was last started
rdbmsSrvInfoFinishedTransactions	Number of transactions completed, either with a commit or with an abort
rdbmsSrvInfoDiskReads	Number of reads from the physical disk
rdbmsSrvInfoLogicalReads	Number of logical reads
rdbmsSrvInfoDiskWrites	Number of writes to the physical disk
rdbmsSrvInfoLogicalWrites	Number of logical writes
rdbmsSrvInfoPageReads	Number of page reads
rdbmsSrvInfoPageWrites	Number of page writes
rdbmsSrvInfoDiskOutOfSpaces	Number of times that the database server or coserver has been unable to obtain the desired disk space
rdbmsSrvInfoHandledRequests	Number of requests made to the database server or coserver on inbound associations
rdbmsSrvInfoRequestRecvs	Number of receive operations that the database server or coserver made while it was processing requests on inbound associations
rdbmsSrvInfoRequestSends	Number of send operations that the database server or coserver made while it was processing requests on inbound associations
rdbmsSrvInfoHighwaterInbound-Associations	Greatest number of inbound associations that have been open at the same time
rdbmsSrvInfoMaxInboundAssociations	Greatest number of inbound associations that can be open at the same time

rdbmsSrvLimitedResourceTable

The following list summarizes this table:

Contents: Information about the limited resources for each database server or coserver

Index: **applIndex, rdbmsSrvLimitedResourceName**

Scope of a row: One limited resource

The table has the following MIB objects.

MIB Object	Description
applIndex	See “ applTable ” on page 3-6.
rdbmsSrvLimitedResourceName	Name of the limited resource: <ul style="list-style-type: none">■ BUFFERS■ DS_MAX_QUERIES■ DS_MAX_SCANS■ DS_TOTAL_MEMORY■ LOCKS■ LTXEHWM■ LTXHWM■ STACKSIZE■ LOGFILES■ DBSPACES■ CHUNKS
rdbmsSrvLimitedResourceID	OID or vendor name for the Informix Private MIB: 1.3.6.1.4.1.893 or informix
rdbmsSrvLimitedResourceLimit	Maximum value that this limited resource can attain
rdbmsSrvLimitedResourceCurrent	Current value for this limited resource

(1 of 2)

MIB Object	Description
rdbmsSrvLimitedResourceHighwater	Maximum value that this limited resource has attained since applUptime was reset. This value is 0 for DBSPACES and CHUNKS.
rdbmsSrvLimitedResourceFailures	Number of times that the database server or coserver tried to exceed the maximum value for this limited resource since applUptime was reset. This value is 0 for DBSPACES and CHUNKS.
rdbmsSrvLimitedResourceDescription	Description of the limited resource. This description includes the units for the value for the limited resource.

(2 of 2)

rdbmsSrvParamTable

The following list summarizes this table:

Contents:	Information about the configuration parameters for each database server or coserver
Index:	applIndex , rdbmsSrvParamName , rdbmsSrvParamSubIndex
Scope of a row:	One configuration parameter that is listed in the configuration file for the database server or coserver

The **ONCONFIG** environment variable specifies the filename of the configuration file. The following table lists the location of the configuration file for each operating system. For more information about the configuration file, see your *Administrator's Guide* and the *Administrator's Reference*. For more information about the **ONCONFIG** environment variable, see the *IBM Informix Guide to SQL: Reference*.

Operating System	Location of Configuration File
UNIX	\$INFORMIXDIR/etc/\$ONCONFIG
Windows	%INFORMIXDIR%\etc\%ONCONFIG%

The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-6.
rdbmsSrvParamName	Name of a configuration parameter
rdbmsSrvParamSubindex	Subindex for the configuration parameter. This value is 1 for every configuration parameter except DATASKIP, DBSPACETEMP, DBSERVERALIASES, and NETTYPE.
rdbmsSrvParamID	OID or vendor name for the Informix Private MIB: 1.3.6.1.4.1.893 or informix
rdbmsSrvParamCurrValue	Value of the configuration parameter. OnSNMP obtains this value from the configuration file. Therefore, it does not reflect dynamic changes that you might make to the configuration parameter.
rdbmsSrvParamComment	Purpose of the configuration parameter

rdbmsSrvTable

The following list summarizes this table:

- Contents: Information about a database server or coserver
- Index: **applIndex**
- Scope of a row: One database server or coserver

The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-6.
rdbmsSrvPrivateMibOID	OID for the Informix Private MIB: 1.3.6.1.4.1.893

MIB Object	Description
rdbmsSrvVendorName	Name of the database server vendor: Informix Software, Inc.
rdbmsSrvProductName	Name of the database server product. For example, this value might be Dynamic Server.
rdbmsSrvContact	Name of the database server contact: informix

(2 of 2)

rdbmsTraps

This MIB object contains information about traps that an SNMP subsystem that supports the RDBMS MIB can generate. In this case, the SNMP subsystem is OnSNMP.

frdbmsStateChange Trap

When a database server changes from its current status to any less-available status, OnSNMP sends a **rdbmsStateChange** trap message to configured network hosts through the master agent.

The following list summarizes this trap:

- Contents: The **rdbmsRelState** MIB object
- Index: **rdbmsDbIndex**, **applIndex**
- Scope of a row: If the status of an Informix database server becomes unavailable, it generates one trap for each database.

For Extended Parallel Server, if the entire database server becomes unavailable, each coserver causes as many traps to be generated as there are available databases.

Online MIB in the Informix Private MIB

The Online MIB defines several tables that provide information that is specifically relevant for Informix database servers, coservers, and their databases.

onActiveBarTable

The following list summarizes this table:

Contents: Information about the current ON-Bar activity

Index: **applIndex, onActiveBarIndex**

Scope of a row: One ON-Bar activity

The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-6 .
onActiveBarIndex	A number that OnSNMP assigns
onActiveBarActivityType	Type of activity: dbspaceBackup (1) dbspaceRestore (2) logBackup (3) logRestore (4) systemBackup (5) systemRestore (6)
onActiveBarActivityLevel	Level of activity: completeBackup (1) incrementalLevelOne (2) incrementalLevelTwo (3)
onActiveBarElapsedTime	Length of time since the activity started, in hundredths of seconds

(1 of 2)

MIB Object	Description
onActiveBarActivitySize	Total number of used pages to scan OnSNMP updates this value as the activity progresses.
onActiveBarActivityScanned	Number of used pages that the activity has scanned so far
onActiveBarActivityCompleted	Number of scanned pages that the activity has transferred for archiving so far
onActiveBarActivityStatus	Status of the activity

(2 of 2)

onActiveTableTable

The following list summarizes this table:

Contents:	Information about the open and active database tables
Index:	applIndex, rdbmsDbIndex, onTableIndex
Scope of a row:	One open and active database table

For a fragmented database table, the values in this table are summaries of the values from all the fragments of the database table. The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-6.
rdbmsDbIndex	See “rdbmsDbTable” on page 3-9.
onTableIndex	See “onDbospaceTable” on page 3-24.
onActiveTableStatus	Status of the table: <ul style="list-style-type: none">■ not Busy (1): The table is not in use.■ busy (2): The table is in use.■ dirty (3): The table has been modified.

(1 of 2)

MIB Object	Description
onActiveTableIsBeingAltered	State of the table: <ul style="list-style-type: none">■ Yes (1): The table is being altered. (An index is being added or dropped, an ALTER TABLE statement is being executed, the alter page count is being updated, or pages are being altered to conform to the latest schema.)■ No (2): The table is not being altered.
onActiveTableUsers	Number of users accessing the table
onActiveTableLockRequests	Number of lock requests
onActiveTableLockWaits	Number of lock waits
onActiveTableLockTimeouts	Number of lock timeouts
onActiveTableIsamReads	Number of reads from the database table
onActiveTableIsamWrites	Number of writes to the database table
onActiveTableBufferReads	Number of buffer reads
onActiveTableBufferWrites	Number of buffer writes

(2 of 2)

onBarTable

The following list summarizes this table:

Contents: Information about the backup and restore history

Index: **applIndex, onBarActivityIndex, onBarObjectIndex**

Scope of a row: One object that participated in a backup or restore activity

For information about backup and restore, see the *Backup and Restore Guide*. The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-6.
onBarActivityIndex	Index to the history
onBarObjectIndex	Index to the object
onBarName	Name of the object
onBarType	Type of object: <ul style="list-style-type: none">■ blobospace (1) <p>(Only Dynamic Server provides blobospaces.)</p> <ul style="list-style-type: none">■ rootDbospace (2)■ criticalDbospace (3)■ noncriticalDbospace (4)■ logicalLog (5)
onBarLevel	Level of the backup action: <ul style="list-style-type: none">■ completeBackup (1)■ incrementalLevelOne(2)■ incrementalLevelTwo (3)

MIB Object	Description
onBarStatus	Status of the action on the object: <ul style="list-style-type: none">■ 0 = successful■ Nonzero = error number
onBarTimeStamp	Ending time stamp for the action

(2 of 2)

onChunkTable

The following list summarizes this table:

Contents:	Information about the chunks that the database servers and coservers use
Index:	applIndex, onDbospaceIndex, onChunkIndex
Scope of a row:	One chunk

The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-6.
onDbospaceIndex	See “rdbmsDbInfoTable” on page 3-8.
onChunkIndex	Unique integer index for this chunk The database server or coserver generates this value.
onChunkFileName	Pathname for the chunk
onChunkFileOffset	Offset into the device, in pages
onChunkPagesAllocated	Chunk size, in pages
onChunkPagesUsed	Number of pages used

(1 of 3)

MIB Object	Description
onChunkType	Type of chunk: <ul style="list-style-type: none">■ regularChunk (1)■ blobChunk (2)■ stageBlob (3)
onChunkStatus	Status of the chunk: <ul style="list-style-type: none">■ offline (1)■ online (2)■ recovering (3)■ inconsistent (4)■ dropped (5)
onChunkMirroring	Mirroring status of the chunk: <ul style="list-style-type: none">■ notMirrored (1)■ mirrored (2)■ newlyMirrored (3)
onChunkReads	Number of physical-read operations
onChunkPageReads	Number of page reads
onChunkWrites	Number of physical-write operations
onChunkPageWrites	Number of page writes
onChunkMirrorFileName	Pathname of the mirror chunk If the chunk is not mirrored, this value is noSuchInstance (SNMPv2) or noSuchName (SNMPv1).
onChunkMirrorFileOffset	Offset of the mirror, in pages If the chunk is not mirrored, this value is noSuchInstance (SNMPv2) or noSuchName (SNMPv1).

MIB Object	Description
onChunkMirrorStatus	Mirroring status: <ul style="list-style-type: none">■ offline (1)■ online (2)■ recovering (3)■ inconsistent (4)■ dropped (5) If the chunk is not mirrored, this value is noSuchInstance (SNMPv2) or noSuchName (SNMPv1).

(3 of 3)

onDatabaseTable

The following list summarizes this table:

Contents: Information about active databases

Index: applIndex, rdbmsDbIndex

Scope of a row: One active database

This table does not provide information about an active database if one of the dbspaces for the database is down. (The **rdbmsRelState** MIB object for each database in **rdbmsRelTable** indicates whether or not a database is active and whether or not one of its dbspaces is down.)

The table has the following MIB objects.

MIB Object	Description
applIndex	See “ applTable ” on page 3-6.
rdbmsDbIndex	See “ rdbmsDbTable ” on page 3-9.
onDatabaseDbSpace	Default dbspace
onDatabaseCreated	Creation date and time

(1 of 2)

MIB Object	Description
onDatabaseLogging	Logging status: <ul style="list-style-type: none">■ none (1)■ buffered (2)■ unbuffered (3)■ ansi (4)
onDatabaseOpenStatus	Database status: <ul style="list-style-type: none">■ notOpen (1)■ open (2)■ openExclusive (3)
onDatabaseUsers	Number of users

(2 of 2)

onDbospaceTable

The following list summarizes this table:

Contents:	Information about dbspaces
Index:	applIndex, onDbospaceIndex
Scope of a row:	One dbspace

The table has the following MIB objects.

MIB Object	Description
applIndex	See “ applTable ” on page 3-6.
onDbospaceIndex	Unique integer index for this dbspace. The database server or coserver generates this value.
onDbospaceName	Name of the dbspace
onDbospaceOwner	Login name of the owner
onDbospaceCreated	Creation date

(1 of 3)

MIB Object	Description
onDbospaceChunks	Number of chunks in the dbospace
onDbospaceType	Type of dbospace: <ul style="list-style-type: none"> ■ regularDbospace (1) ■ temporaryDbospace (2) ■ blobDbospace (3)
onDbospaceMirrorStatus	Mirroring status: <ul style="list-style-type: none"> ■ notMirrored (1) ■ mirrored (2) ■ mirrorDisabled (3) ■ newlyMirrored (4)
onDbospaceRecoveryStatus	Recovery status: <ul style="list-style-type: none"> ■ noRecoveryNeeded (1) ■ doneRecovery (2) ■ physicallyRecovered (3) ■ logicallyRecovering (4)
onDbospaceBackupStatus	Backup status: <ul style="list-style-type: none"> ■ yes (1): The dbospace is backed up. ■ no (2): The dbospace is not backed up.
onDbospaceMiscStatus	Miscellaneous status: <ul style="list-style-type: none"> ■ none (1): no more information ■ aTableDropped (2)
onDbospacePagesAllocated	Size of all the primary chunks in the dbospace
onDbospacePagesUsed	Number of pages used in all the primary chunks in the dbospace

(2 of 3)

MIB Object	Description
onDbospaceBackupDate	Date when the latest backup was performed. If the dbospace has never been backed up, this value is noSuchInstance (SNMPv2) or noSuchName (SNMPv1).
onDbospaceLastBackupLevel	Level of the last backup. If the dbospace has never been backed up, this value is noSuchInstance (SNMPv2) or noSuchName (SNMPv1).
onDbospaceLastFullBackupDate	Date and time of the last full backup (level 0). If the dbospace has never had a full backup, this value is noSuchInstance (SNMPv2) or noSuchName (SNMPv1).

(3 of 3)

onErQueueTable

The following list summarizes this table:

Contents: Information about the replication queues for all database servers that participate in Enterprise Replication

Index: **applIndex, onErQueueReplIndex**

Scope of a row: One replication queue

The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-6 .
onErQueueReplIndex	Unique integer index that identifies a replicant
onErQueueSiteIndex	Unique integer that identifies a database server
onErQueueReplName	Display string that describes the replicant or collection of replicants
onErQueueSiteName	Name of the Enterprise Replication database server

(1 of 2)

MIB Object	Description
onErQueueSize	Current number of bytes in the send queue
onErQueueLastCommit	Date and time when last transaction was committed
onErQueueLastAck	Date and time when last data was acknowledged

(2 of 2)

onErSiteTable

The following list summarizes this table:

Contents: Information about all the remote database servers that participate in Enterprise Replication

Index: **applIndex, onErSiteIndex**

Scope of a row: A single replication queue

The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-6 .
onErSiteIndex	Integer that uniquely identifies a database server as defined in the group entry in sqlhosts
onErSiteName	Name of the replication site

(1 of 3)

MIB Object	Description
onErSiteState	State of the replication activity for this site: <ul style="list-style-type: none">■ inactive (1)■ active (2)■ suspend (3)■ quiescent (4)■ hold (5)■ delete (6)■ failed (7)■ unknown (8)
onErSiteConnectionState	State of the connection to this site: <ul style="list-style-type: none">■ idle (1)■ connected (2)■ disconnected (3)■ timeout (4)■ shutdown (5)■ error (6)■ unknown (7)
onErSiteConnectionChange	Date and time when the connection state last changed
onErSiteIdleTimeout	Time limit for Enterprise Replication to wait for new data to send or receive. Value is set when database server is defined. Connection is closed if time limit is exceeded.
onErSiteOutMsgs	Total number of messages transmitted from the current database server to this site
onErSiteOutBytes	Total number of bytes transmitted from the current database server to this site
onErSiteInMsgs	Total number of messages received by the current database server from this site
onErSiteInBytes	Total number of bytes received by the current database server from this site
onErSiteTransactions	Total number of transactions received from this site

MIB Object	Description
onErSiteCommits	Total number of transactions received and committed from this site
onErSiteAborts	Total number of transactions aborted from this site
onErSiteLastReceived	Date and time when the last transaction was processed from this site
onErSiteRowCommits	Total number of rows committed from this site
onErSiteRowAborts	Total number of rows aborted from this site
onErSiteRcvLatency	Average latency between the source commit time and target receive time; performance measure of network queueing delay
onErSiteCommitLatency	Average latency between source and target commit time; performance measure of network and database server delay
onErSiteClockErrors	Number of transactions received from this site with a time that is ahead of our current time; indicates system clock synchronization problems

(3 of 3)

onFragmentTable

The following list summarizes this table:

- Contents:

Information about the fragments that are in fragmented database tables
- Index:

applIndex, **rdbmsDbIndex**, **onTableIndex**, **onFragmentIndex**
- Scope of a row:

One fragment of a fragmented database table

The table has the following MIB objects.

MIB Object	Description
applIndex	See “ applTable ” on page 3-6.
rdbmsDbIndex	See “ rdbmsDbTable ” on page 3-9.
onTableIndex	See “ onDbospaceTable ” on page 3-24.

(1 of 2)

MIB Object	Description
onFragmentIndex	Unique integer index for the fragment
onFragmentType	Type of database table: <ul style="list-style-type: none">■ fragmentedIndex (1)■ fragmentedTable (2)
onFragmentDbpace	Dbpace name for the fragment
onFragmentExpression	Expression text used for fragmentation of the table or index This value is blank if the fragmentation scheme is round-robin.
onFragmentIndexName	Index identifier
onFragmentExtents	Number of extents used
onFragmentPagesAllocated	Total (extent) size allocated to the fragment, in pages
onFragmentPagesUsed	Number of pages used
onFragmentIsamReads	Number of reads from the fragment If the fragment is not active, this value is noSuchInstance (SNMPv2) or noSuchName (SNMPv1).
onFragmentIsamWrites	Number of writes to the fragment If the fragment is not active, this value is noSuchInstance (SNMPv2) or noSuchName (SNMPv1).
onFragmentUsers	Number of user threads that access the fragment.
onFragmentLockRequests	Number of locks of any type requested for this fragment.
onFragmentLockWaits	Number of times an initial lock request failed because the lock could not be granted initially for the fragment.
onFragmentLockTimeouts	Number of deadlock timeouts for the fragment.

(2 of 2)

onLockTable

The following list summarizes this table:

- Contents:Information about the active locks that database servers and coservers are using
- Index:applIndex, onSessionIndex, onLockIndex
- Scope of a row:One lock
- A row exists for each lock that the session is using and for each lock on which the session is waiting.

The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-6.
onSessionIndex	See “onServerTable” on page 3-34.
onLockIndex	Index to this row
onLockDatabaseName	Name of the database that is using or waiting for this lock
onLockTableName	Name of the table that is using or waiting for this lock
onLockType	Type of the lock: <div><div>■ byte (1)</div><div>■ intentShared (2)</div><div>■ shared (3)</div><div>■ sharedByRepeatableRead (4)</div><div>■ update (5)</div><div>■ intentExclusive (6)</div><div>■ sharedIntentExclusive (7)</div><div>■ exclusive (8)</div><div>■ exclusiveByRepeatableRead (9)</div><div>■ waiting (10)</div></div>

MIB Object	Description
onLockGranularity	Granularity of the lock: <ul style="list-style-type: none">■ table (1)■ page (2)■ row (3)■ index (4)
onLockRowId	rowid of the locked row
onLockWaiters	Number of sessions that are waiting for the lock
onLockGrantTime	Time when the lock was granted if the session is using the lock If no transaction exists, this value is noSuchInstance (SNMPv2) or noSuchName (SNMPv1).

(2 of 2)

onLogicalLogTable

The following list summarizes this table:

Contents:	Information about logical logs
Index:	applIndex, onLogicalLogIndex
Scope of a row:	One logical log

The table has the following MIB objects.

MIB Object	Description
applIndex	See “ applTable ” on page 3-6.
onLogicalLogIndex	Index for the logical-log file
onLogicalLogID	Unique integer identification number for the logical-log file
onLogicalLogDbSPACE	DbSPACE name where the log file was created

(1 of 2)

MIB Object	Description
onLogicalLogStatus	Status of the logical-log file: <ul style="list-style-type: none"> ■ newlyAdded (1) ■ free (2) ■ current (3) ■ used (4) ■ backedUpButNeeded (5)
onLogicalLogContainsLastCheckpoint	Checkpoint status: <ul style="list-style-type: none"> ■ yes (1): The logical-log file contains the last checkpoint. ■ no (2): The logical-log file does not contain the last checkpoint.
onLogicalLogIsTemporary	Temporary status: <ul style="list-style-type: none"> ■ yes (1): The logical-log file is temporary. ■ no (2): The logical-log file is not temporary.
onLogicalLogPagesAllocated	Size of the logical-log file, in pages
onLogicalLogPagesUsed	Number of pages used in the logical-log file
onLogicalLogFillTime	Date and time when the logical-log file last filled up If the log file has never been full, this value is <code>noSuchInstance</code> (SNMPv2) or <code>noSuchName</code> (SNMPv1).
onLogicalLogTimeUniqueIDChanged	Time stamp when a new unique ID was assigned to this logical-log entry
onLogicalLogTimeLastBackupDate	Date and time of the last backup for this logical-log entry

(2 of 2)

onPhysicalLogTable

The following list summarizes this table:

Contents:	Information about physical logs
Index:	applIndex
Scope of a row:	One physical log

The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-6.
onPhysicalLogDbSPACE	DbSPACE name where the physical log was created
onPhysicalLogBufferSize	Size of the physical-log buffer, in pages
onPhysicalLogBufferUsed	Number of pages of the physical-log buffer that are used
onPhysicalLogPageWrites	Number of pages written to the physical log
onPhysicalLogWrites	Number of (disk) writes to the physical log
onPhysicalLogPagesAllocated	Size of the physical log, in pages
onPhysicalLogPagesUsed	Number of pages used

onServerTable

The following list summarizes this table:

Contents:	Status and profile information about each active data-base server and coserver
Index:	applIndex
Scope of a row:	One database server or coserver

The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-6
onServerMode	Mode of the database server or coserver: <ul style="list-style-type: none"> ■ initializing (1) ■ quiescent (2) ■ fastRecovery (3) ■ backingUp (4) ■ shuttingDown (5) ■ online (6) ■ aborting (7) ■ onlineReadOnly (8)
onServerCheckpointInProgress	Checkpoint status: <ul style="list-style-type: none"> ■ yes (1): A checkpoint is in progress. ■ no (2): A checkpoint is not in progress.
onServerPageSize	Size of a page, in bytes
onServerThreads	Number of active threads
onServerVPs	Number of virtual processors
onServerVirtualMemory	Total virtual memory used, in kilobytes
onServerResidentMemory	Total resident memory used, in kilobytes
onServerMessageMemory	Total message memory used, in kilobytes
onServerIsamCalls	Sum of all reads, writes, rewrites, deletes, commits, and rollbacks to and from the database table
onServerLatchWaits	Number of latch waits
onServerLockRequests	Number of lock requests
onServerLockWaits	Number of lock waits
onServerBufferWaits	Number of buffer waits

(1 of 3)

MIB Object	Description
onServerCheckpointWaits	Number of checkpoint waits
onServerDeadLocks	Number of deadlocks
onServerLockTimeouts	Number of deadlock time-outs
onServerLogicalLogRecords	Number of logical-log records
onServerLogicalLogPageWrites	Number of logical-log page writes
onServerLogicalLogWrites	Number of logical-log writes
onServerBufferFlushes	Number of buffer flushes
onServerForegroundWrites	Number of foreground writes
onServerLRUWrites	Number of LRU writes
onServerChunkWrites	Number of chunk writes
onServerReadAheadPages	Number of read-ahead pages This value includes data and index read-ahead pages.
onServerReadAheadPagesUsed	Number of read-ahead pages used
onServerSequentialScans	Number of sequential scans
onServerMemorySorts	Number of memory sorts
onServerDiskSorts	Number of disk sorts
onServerMaxSortSpace	Maximum disk space that a sort uses, in pages
onServerNetworkReads	Number of network reads
onServerNetworkWrites	Number of network writes
onServerPDQCalls	Number of parallel-processing actions performed
onServerTransactionCommits	Number of committed transactions
onServerTransactionRollbacks	Number of rolled-back transactions

MIB Object	Description
onServerTimeSinceLastCheckpoint	Length of time since the last checkpoint, in hundredths of second
onServerCPUSystemTime	Amount of CPU time that the database server has used in System Mode, in hundredths of second
onServerCPUUserTime	Amount of CPU time that the database server has used in User Mode, in hundredths of second

(3 of 3)

onSessionTable

The following list summarizes this table:

Contents:	Information about each session
Index:	applIndex, onSessionIndex
Scope of a row:	One session

The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-6 .
onSessionIndex	Unique integer index for the session
onSessionUserName	Name of the user, in the form name@host (tty)
onSessionUserProgramVersion	Version of the database server or coserver
onSessionUserProcessId	Process ID for the session
onSessionUserTime	Length of time that the user has been connected to the database server or coserver, in hundredths of seconds

(1 of 4)

MIB Object	Description
onSessionState	State of the session: <ul style="list-style-type: none"> ■ idle (1) ■ active (2) ■ waitingOnMutex (3) ■ waitingOnCondition (4) ■ waitingOnLock (5) ■ waitingOnBuffer (6) ■ waitingOnCheckPointing (7) ■ waitingOnLogicalLogWrite (8) ■ waitingOnTransaction (9)
onSessionDatabase	Connected database
onSessionCurrentMemory	Memory usage, in bytes
onSessionThreads	Number of active threads
onSessionCurrentStack	Average size of the stack for all threads
onSessionHighwaterStack	Maximum amount of memory that any thread has used so far
onSessionLockRequests	Number of lock requests
onSessionLocksHeld	Number of locks held
onSessionLockWaits	Number of lock waits
onSessionLockTimeouts	Number of time-outs for locks
onSessionLogRecords	Number of log records
onSessionIsamReads	Number of reads from database tables
onSessionIsamWrites	Number of writes to database tables
onSessionPageReads	Number of page reads
onSessionPageWrites	Number of page writes
onSessionLongTx	Number of long transactions
onSessionLogSpace	Logical-log space used, in bytes

MIB Object	Description
onSessionHighwaterLogSpace	Maximum logical-log space that this session has ever used
onSessionSqlStatement	Latest SQL statement, truncated to 250 characters if necessary
onSessionSqlIsolation	SQL isolation level: <ul style="list-style-type: none"> ■ noTransactions (1) ■ dirtyReads (2) ■ readCommitted (3) ■ cursorRecordLocked (4) ■ repeatableRead (5)
onSessionSqlLockWaitMode	Action to take if the isolation level requires a wait: <ul style="list-style-type: none"> ■ -1 = Wait forever. ■ 0 = Do not wait. ■ >0 = Wait for specified number of seconds.
onSessionSqlEstimatedCost	Estimated cost of the SQL statement according to SQLEXPLAIN
onSessionSqlEstimatedRows	Estimated number of rows that the SQL statement will select according to SET EXPLAIN
onSessionSqlError	Error number for the last SQL statement
onSessionSqlIsamError	ISAM error number for the last SQL statement
onSessionTransactionStatus	Status of the transaction: <ul style="list-style-type: none"> ■ none (1) ■ committing (2) ■ rollingBack (3) ■ rollingHeuristically (4) ■ waiting (5)
onSessionTransactionBeginLog	Unique ID of the logical-log file in which the BEGIN WORK record was logged If no transaction exists, this value is noSuchInstance (SNMPv2) or noSuchName (SNMPv1).

(3 of 4)

MIB Object	Description
onSessionTransactionLastLog	Unique ID of the logical-log file in which the last record was logged If no transaction exists, this value is noSuchInstance (SNMPv2) or noSuchName (SNMPv1).
onSessionOriginatingCoserverId (XPS)	Coserver ID of the coserver for which this local session runs
onSessionOriginatingSessionId	Local session ID of the global session on the coserver for which this local session runs

(4 of 4)

onSqlHostTable

- The following list summarizes this table:
- Contents: Copy of the connection information
- Index: applIndex, onSqlHostIndex
- Scope of a row: One connectivity value

As the following table shows, the location of the connection information depends on the operating system. For details about the connection information, see your *Administrator's Guide*.

Operating System	Location of Connectivity Information
UNIX	The INFORMIXSQLHOSTS environment variable specifies the full pathname and filename of the connection information. The default location is \$INFORMIXDIR/etc/sqlhosts . For information about INFORMIXSQLHOSTS , see the <i>IBM Informix Guide to SQL: Reference</i> .
Windows	The connectivity information is in a key in the Windows registry called HKEY_LOCAL_MACHINE\SOFTWARE\Informix\SQLHOSTS .

The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-6.
onSqlHostIndex	Index to the entry in the connectivity information
onSqlHostName	Host name of the database server or coserver
onSqlHostNetType	Connection type
onSqlHostServerName	Name of the database server or coserver or its alias
onSqlHostServiceName	Service name
onSqlHostOptions	List server options in the form of <code>key=value</code> pairs

onTableTable

The following list summarizes this table:

- Contents: Information about a database table
- Index: **applIndex, rdbmsDbIndex, onTableIndex**
- Scope of a row: One database table

For a fragmented database table, the values in this table are summaries of the values from all the database table fragments. The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-6.
rdbmsDbIndex	See “rdbmsDbTable” on page 3-9.
onTableIndex	Table number This value is the same as tabid in the system catalog table systables
onTableName	Table name

MIB Object	Description
onTableOwner	Table owner
onTableType	Type of table: <ul style="list-style-type: none">■ table (1)■ view (2)■ privateSynonym (3)■ synonym (4)
onTableLockLevel	Locking level of the table: <ul style="list-style-type: none">■ page (1)■ row (2)
onTableCreated	Creation date, in string format
onTableFirstDbospace	Name of the first (or only) dbospace for the table
onTableRowSize	Length of a row
onTableRows	Number of rows
onTableColumns	Number of columns
onTableIndices	Number of indexes
onTableExtents	Number of extents in use
onTablePagesAllocated	Total (extent) size allocated to the table, in pages
onTablePagesUsed	Number of pages in use
onTableFragments	Number of fragments

(2 of 3)

MIB Object	Description
onTableFragmentStrategy	Fragmentation strategy: <ul style="list-style-type: none">■ roundRobin (1)■ byExpression (2)■ tableBased (3) If the table is not fragmented, this value is noSuchInstance (SNMPv2) or noSuchName (SNMPv1).
onTableActiveFragments	Number of active fragments If the table is not fragmented, this value is noSuchInstance (SNMPv2) or noSuchName (SNMPv1).

(3 of 3)

XPS

onXpsTable

The following list summarizes this table:

- Contents:
- The OnSNMP instance that is the subagent for Extended Parallel Server
- Index:
- applIndex
- Scope of a row:
- One coserver

For information about the subagent, see [“SNMP and Extended Parallel Server” on page 2-27](#). The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-6 .
onXpsSnmpIndex	<div>Unique integer index that identifies the subagent. This value is the sum of the following values:</div> <div><div>■ Informix Enterprise ID * 1,000,000</div><div>The Informix Enterprise ID is 893. Therefore, Informix Enterprise ID * 1,000,000 is 893,000,000.</div><div>■ SERVERNUM * 1000</div><div>■ Coserver ID</div></div>
onXpsSnmpHost	Name of the workstation on which the subagent runs

XPS MIB in the Informix Private MIB

The XPS MIB defines several tables that provide information that is specifically relevant for database servers, coservers, and their databases on Extended Parallel Server.

xpsCogroupMemberTable

The following list summarizes this table:

- Contents: Information about coservers as members of cogroups
- Index: **applIndex**, **xpsCogroupIndex**,
xpsCogroupMemberIndex
- Scope of a row: One coserver
- The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-6 .
xpsCogroupIndex	See “xpsCogroupTable” on page 3-45 .
xpsCogroupMemberIndex	Unique integer index that identifies the coserver
xpsCogroupMemberCoserverId	Coserver ID

xpsCogroupTable

The following list summarizes this table:

- Contents: Information about cogroups as members of Extended Parallel Server
- Index: **applIndex**, **xpsCogroupIndex**
- Scope of a row: One cogroup

The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-6.
xpsCogroupIndex	Unique integer index that identifies the cogroup
xpsCogroupName	Name of the cogroup
xpsCogroupMemberCount	Number of coservers that are in the cogroup
xpsCogroupIsClustered	Indicates whether or not the cogroup is clustered: <ul style="list-style-type: none">■ yes (1)■ no (2)

xpsCoserverTable

The following list summarizes this table:

- Contents:

Information about coservers as members of Extended Parallel Server
- Index:

applIndex, xpsCoserverIndex
- Scope of a row:

One coserver

The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-6.
xpsCoserverIndex	Unique integer index that identifies the coserver. This value is the sum of the following values: <ul style="list-style-type: none">■ Informix Enterprise ID * 1,000,000 <p>The Informix Enterprise ID is 893. Therefore, Informix Enterprise ID * 1,000,000 is 893,000,000.</p> <ul style="list-style-type: none">■ SERVERNUM * 1000■ Coserver ID
xpsCoserverHostname	Name of the workstation on which the coserver runs
xpsCoserverId	Coserver ID
xpsCoserverRootDbospaceId	ID of the root dbospace for the coserver

xpsDbsliceDbospaceTable

The following list summarizes this table:

Contents:	Information about each dbospace that is in Extended Parallel Server
Index:	applIndex , xpsDbsliceIndex , xpsDbsliceDbospaceIndex
Scope of a row:	One dbospace

The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-6.
xpsDbsliceIndex	See “xpsDbsliceTable” on page 3-48.
xpsDbsliceDbSPACEIndex	Unique integer index that identifies the dbSPACE
xpsDbsliceDbSPACE	Coserver ID for the connecting coserver

xpsDbsliceTable

The following list summarizes this table:

Contents:	Information about each dbslice that is in Extended Parallel Server
Index:	applIndex, xpsDbsliceIndex
Scope of a row:	One dbslice

The table has the following MIB objects.

MIB Object	Description
applIndex	See “applTable” on page 3-6.
xpsDbsliceIndex	Unique integer index that identifies the dbslice
xpsDbsliceName	Name of the dbslice
xpsDbsliceDbSPACESCount	Number of dbSPACES in the dbslice
xpsDbsliceIsMirrored	Indicates whether or not the dbslice is mirrored: <ul style="list-style-type: none">■ yes (1)■ no (2)

MIB Object	Description
xpsDbsliceIsBlobSlice	Indicates whether or not the dbslice is a blobslice: <ul style="list-style-type: none">■ yes (1)■ no (2)
xpsDbsliceIsTemp	Indicates whether or not the dbslice is temporary: <ul style="list-style-type: none">■ yes (1)■ no (2)

(2 of 2)

Notices

IBM may not offer the products, services, or features discussed in this document in all countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing
IBM Corporation
North Castle Drive
Armonk, NY 10504-1785
U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

IBM World Trade Asia Corporation
Licensing
2-31 Roppongi 3-chome, Minato-ku
Tokyo 106-0032, Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law:

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation
J46A/G4
555 Bailey Avenue
San Jose, CA 95141-1003
U.S.A.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this information and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement, or any equivalent agreement between us.

Any performance data contained herein was determined in a controlled environment. Therefore, the results obtained in other operating environments may vary significantly. Some measurements may have been made on development-level systems and there is no guarantee that these measurements will be the same on generally available systems. Furthermore, some measurements may have been estimated through extrapolation. Actual results may vary. Users of this document should verify the applicable data for their specific environment.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

All IBM prices shown are IBM's suggested retail prices, are current and are subject to change without notice. Dealer prices may vary.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. You may copy, modify, and distribute these sample programs in any form without payment to IBM for the purposes of developing, using, marketing, or distributing application programs conforming to IBM's application programming interfaces.

Each copy or any portion of these sample programs or any derivative work, must include a copyright notice as follows:

© (your company name) (year). Portions of this code are derived from IBM Corp. Sample Programs. © Copyright IBM Corp. (enter the year or years). All rights reserved.

If you are viewing this information softcopy, the photographs and color illustrations may not appear.

Trademarks

AIX; DB2; DB2 Universal Database; Distributed Relational Database Architecture; NUMA-Q; OS/2, OS/390, and OS/400; IBM Informix®; C-ISAM®; Foundation.2000™; IBM Informix® 4GL; IBM Informix® DataBlade® Module; Client SDK™; Cloudscape™; Cloudsync™; IBM Informix® Connect; IBM Informix® Driver for JDBC; Dynamic Connect™; IBM Informix® Dynamic Scalable Architecture™ (DSA); IBM Informix® Dynamic Server™; IBM Informix® Enterprise Gateway Manager (Enterprise Gateway Manager); IBM Informix® Extended Parallel Server™; i.Financial Services™; J/Foundation™; MaxConnect™; Object Translator™; Red Brick Decision Server™; IBM Informix® SE; IBM Informix® SQL; InformiXML™; RedBack®; SystemBuilder™; U2™; UniData®; UniVerse®; wintegrate® are trademarks or registered trademarks of International Business Machines Corporation.

Java and all Java-based trademarks and logos are trademarks or registered trademarks of Sun Microsystems, Inc. in the United States and other countries.

Windows, Windows NT, and Excel are either registered trademarks or trademarks of Microsoft Corporation in the United States and/or other countries.

UNIX is a registered trademark in the United States and other countries licensed exclusively through X/Open Company Limited.

Other company, product, and service names used in this publication may be trademarks or service marks of others.

Glossary

agent	An interface to a managed object, such as a workstation or an application running on a workstation, that responds to a request from a manager.
ASN.1	Acronym for Abstract Syntax Notation One, a standard language for describing data structures. ASN.1 does not depend on computer architecture or implementation language. Therefore, it lets programs exchange structured data over networks. For more information, see “MIBs” on page 1-9 .
coserver	The functional equivalent of a database server that operates on a single node. References to coserver in this manual apply only to Extended Parallel Server.
IANA	Acronym for Internet Assigned Numbers Authority, which defines a hierarchy for naming tables and columns and for deriving numerical object identifiers (OIDs). IANA assigns identifiers to companies that use the SNMP protocol.
IETF	Acronym for Internet Engineering Task Force, which specifies the structure of public MIBS and MIB tables.
infxsnmp.dll	Library for the Windows version of OnSNMP.
managed component	Hardware or software component that has a corresponding SNMP subagent. To manage a component, an SNMP Network Manager communicates with a master agent, and the master agent communicates with a subagent.
managed workstation	Workstation that includes a managed component.

master agent	Program that provides an interface between a subagent and an SNMP Network Manager. A managed workstation includes one master agent.
MIB	Acronym for Management Information Base, which is a group of tables that contain the information that a subagent can provide to a master agent.
OID	Acronym for Object Identifier, which is a numerical value that identifies an MIB, an MIB table, a parameter (column) in an MIB table, or an object (row) in an MIB table.
onsnmp	Subagent program for the UNIX version of OnSNMP.
onsnmp.exe	Subagent program for the Windows version of OnSNMP.
OnSNMP	Subagent for an Informix database server or coserver. On UNIX, OnSNMP consists of onsnmp . In Windows, OnSNMP consists of onsnmp.exe , infxsnmp.dll , and onsrvapd.exe .
onsrvapd	Server discovery program for the UNIX version of OnSNMP.
onsrvapd.exe	Server discovery program for the Windows version of OnSNMP.
runsnmp.ksh	Helper script to ensure that both the onsrvapd server discovery daemon and the SNMP master agent are running on a host.
Server Discovery Process	The discovery process discovers multiple server instances running on the host. These instances might belong to different versions that are installed on different directories.
SMI	In the context of SNMP, acronym for the Structure of Management Information, which defines the common interface definition language.
SNMP	Acronym for Simple Network Management Protocol, a communication protocol that lets you manage components on a network.
SNMP Network Manager	Program that monitors and controls managed components on a network.
SNMPv1, SNMPv2	Versions of the SNMP standard. For more information, see “SNMP Standard” on page 2-7 .
subagent	Program that lets a managed component and a master agent communicate with each other.

Index

A

Abstract Syntax Notation One. *See* ASN.1.
 ANSI compliance
 level Intro-14
 Application MIB
 location in hierarchy 2-29
 reference 3-6
 APPLMIB registry argument 2-24
 applTable 3-6
 ASN.1, description 1-9

B

Boldface type Intro-6

C

Code set, ISO 8859-1 Intro-4
 Command
 grep 2-15
 inssnmp 2-26
 onsrvapd 2-19, 2-20, 2-35
 runsnmp.ksh 2-12
 snmpdm 2-16
 snmpdp 2-16
 Command-line conventions
 elements of Intro-9
 example diagram Intro-10
 how to read Intro-10
 Comment icons Intro-7
 Compliance
 with industry standards Intro-14
 Configuration
 EMANATE master agent 2-14

 file location 3-14
 for traps 1-9
 master agent 2-14
 OnSNMP 2-18, 2-24
 parameter files 3-14
 Patrol master agent 2-15
 Connectionless protocol 1-5
 Contact information Intro-14
 Conventions,
 documentation Intro-6

D

Data requests
 example 2-5
 general description 1-9
 Informix implementation 2-4
 Database servers
 configuration parameters 3-14
 locks 3-31
 See also Managed components.
 Database tables, fragmented 3-29
 Databases
 general information 3-8
 sysmaster 2-6
 sysutils 2-6
 DB-Access utility Intro-5
 Dbspaces 3-24
 Default locale Intro-4
 Demonstration databases Intro-5
 Dependencies, software Intro-4
 Directory
 for MIB files 3-3
 for Windows Subagent 2-23
 SNMP 2-12
 Documentation notes Intro-12

Documentation notes, program item Intro-13

Documentation, types of Intro-11

documentation notes Intro-12

machine notes Intro-12

release notes Intro-12

E

EMANATE master agent 2-13

Enterprise Replication 3-26, 3-27

Environment variables Intro-6

 INFORMIXDIR 2-12

 INFORMIXSQLHOSTS 3-40

 ONCONFIG 3-14

 PATH 2-14, 2-15

 SR_AGT_CONF_DIR 2-14

 SR_LOG_DIR 2-14

en_us.8859-1 locale Intro-4

Error -23101 2-28

Error message

 EMANATE log file 2-17

 turning on 2-17

Event notification

 example 2-4

 general description 1-8

 Informix implementation 2-4

F

Feature icons Intro-8

Features of this product, new Intro-5

Files

 EMANATE log 2-17

 infxsnmp.dll 2-23

 installed on UNIX 2-36

 installed on Windows 2-37

 location of configuration 3-14

 MIB directory 3-3

 onsnmp.exe 2-23

 onsrvapd.exe 2-23

 runsnmp.ksh 2-12

finderr utility Intro-13

Fragmented database tables 3-29

G

Global Language Support (GLS) and SNMP 2-28

H

Help Intro-11

Hierarchy of MIBs. *See* MIBs hierarchy.

I

IANA. *See* Internet Assigned Numbers Authority.

Icons

 feature Intro-8

 Important Intro-7

 platform Intro-8

 product Intro-8

 Tip Intro-7

 Warning Intro-7

IETF. *See* Internet Engineering Task Force.

Important paragraphs, icon for Intro-7

Industry standards, compliance with Intro-14

Informix Private MIB, location in hierarchy 2-31

INFORMIXDIR/bin directory Intro-5

INFXSNMP registry argument 2-24

infxsnmp.dll file, description 2-23

inssnmp program 2-26

Installation

 files for UNIX and Windows 2-36

 master agent on UNIX 2-14

 master agent on Windows 2-22

 required software 2-11, 2-21

 subagent on UNIX 2-18

 subagent on Windows 2-23

Internet Assigned Numbers Authority 1-10, 2-31

Internet Engineering Task Force 2-29

ISO 8859-1 code set Intro-4

L

LINGER_TIME registry argument 2-24

Locale Intro-4

 default Intro-4

 en_us.8859-1 Intro-4

Locks 3-31

LOGDIR registry argument 2-24

Logical logs 3-32

LOGLEVEL registry argument 2-24

Logs

 logical 3-32

 physical 3-33

M

Machine notes Intro-12

Managed components

 general description 1-8

 in SNMP architecture 1-4

 Informix implementation 2-3

Management Information Bases. *See* MIBs.

Master agents

 configuring on UNIX 2-14

 EMANATE 2-13

 general description 1-7

 in SNMP architecture 1-4

 Informix implementation on UNIX 2-13

 on Windows 2-22

 installing on UNIX 2-14

 Patrol 2-13

 starting on UNIX 2-16

 stopping on UNIX 2-16

Message file for error messages Intro-13

MIB tables. *See* MIBs.

MIBs

 general description 1-9

 hierarchy 1-10, 2-31

 in SNMP architecture 1-4

 indexing 2-33

 Informix implementation 2-29

 naming conventions 1-9

 reference 3-3

summary of tables 3-3
tables 3-3 to 3-48

N

Network managers. *See* SNMP
network managers.
New features of this
product Intro-5

O

Object Identifiers. *See* OIDs.
OIDs
 definition 1-11
 in MIB hierarchy 1-10
onActiveBarTable 3-17
onBarTable 3-20
onChunkTable 3-21
onDatabaseTable 3-23
onDbSpaceTable 3-24
onErQueueTable 3-26
onErSiteTable 3-27
onFragmentTable 3-29
Online help Intro-11
Online manuals Intro-11
Online MIB
 location in hierarchy 2-32
 reference 3-17
onLockTable 3-31
onLogicalLogTable 3-32
ONMIB registry argument 2-24
onPhysicalLogTable 3-33
onServerTable 3-34
onSessionTable 3-37
OnSnmpSubagent registry
 key 2-24
OnSNMP. *See* Subagents.
onsnmp. *See* Subagents.
onsnmp.exe file, description 2-23
onSqlHostTable 3-40
onsrvapd
 arguments 2-12, 2-20
 server-discovery daemon 2-12
 starting on UNIX 2-18
 stopping on UNIX 2-18
onsrvapd.exe file, description 2-23
onstat utility 2-6

onTableTable 3-41
onXpsTable 3-44

P

PATH environment variable 2-14,
 2-15
Pathname registry argument 2-24
Patrol master agent 2-13
Physical logs 3-33
Platform icons Intro-8
Product icons Intro-8
Program
 inssnmp 2-26
 master agent 1-7
 onsnmp 2-18
 SNMP network manager 1-5
 subagent 1-8
Program group
 Documentation notes Intro-13
 Release notes Intro-13

R

RDBMS MIB
 location in hierarchy 2-30
 reference 3-8
rdbmsDbInfoTable 3-8
rdbmsDbLimitedResourceTable
 3-9
rdbmsDbParamTable 3-9
rdbmsDbTable 3-9
RDBMSMIB registry
 argument 2-24
rdbmsRelTable 3-10
rdbmsSrvInfoTable 3-11
rdbmsSrvLimitedResourceTable
 3-13
rdbmsSrvParamTable 3-14
rdbmsSrvTable 3-15
rdbmsTraps 3-16
REFRESH_TIME registry
 argument 2-24
Registry arguments
 APPLMIB 2-24
 INFXSMP 2-24
 LINGER_TIME 2-24
 LOGDIR 2-24

LOGLEVEL 2-24
ONMIB 2-24
Pathname 2-24
RDBMSMIB 2-24
REFRESH_TIME 2-24
XPSMIB 2-24
Registry key,
 OnSnmpSubagent 2-24
Release notes Intro-12
Release notes, program
 item Intro-13
runsnmp.ksh script 2-12

S

sales_demo database Intro-5
Script, runsnmp.ksh 2-12
Server discovery process
 definition of 2-11
 See also onsrvapd.
SMI. *See* Structure of Management
 Information.
SNMP
 general description 1-3
 purpose 1-3, 2-4
 versions 2-7
SNMP architecture
 general description 1-4
 Informix implementation on
 UNIX 2-7
 Informix implementation on
 Windows 2-9
SNMP network managers
 examples 1-6 to 1-7
 general description 1-5
 in SNMP architecture 1-4
 vendors 1-5
Software dependencies Intro-4
SR_AGT_CONF_DIR environment
 variable 2-14
SR_LOG_DIR environment
 variable 2-14
stores_demo database Intro-5
Structure of Management
 Information 1-9
Subagents
 configuring on Windows 2-24
 general description 1-8

in SNMP architecture 1-4
 information provided by
 OnSNMP 2-6
 Informix implementation
 on UNIX 2-18
 on Windows 2-23
 installing
 on UNIX 2-18
 on Windows 2-23
 starting
 on UNIX 2-18
 on Windows 2-23
 stopping
 on UNIX 2-18
 on Windows 2-23
 superstores_demo database Intro-5
 Syntax
 onsrvapd 2-19
 runsnmp.ksh 2-12
 System requirements
 database Intro-4
 software Intro-4

T

Table
 MIB, event column 2-4
 MIB, naming 1-9
 system catalog 2-6
 Table, application MIB
 applTable 3-6
 Table, Online MIB
 onActiveBarTable 3-17
 onActiveTableTable 3-18
 onBarTable 3-20
 onChunkTable 3-21
 onDatabaseTable 3-23
 onDbospaceTable 3-24
 onErQueueTable 3-26
 onErSiteTable 3-27
 onFragmentTable 3-29
 onLockTable 3-31
 onLogicalLogTable 3-32
 onPhysicalLogTable 3-33
 onServerTable 3-34
 onSessionTable 3-37
 onSqlHostTable 3-40
 onTableTable 3-41

 onXpsTable 3-44
 Table, RDBMS MIB
 rdbmsDbInfoTable 3-8
 rdbmsDbTable 3-9
 rdbmsRelTable 3-10
 rdbmsSrvInfoTable 3-11
 rdbmsSrvLimitedResourceTable
 3-13
 rdbmsSrvParamTable 3-14
 rdbmsSrvTable 3-15
 Table, Xps MIB
 XpsCogroupMemberTable 3-45
 XpsCogroupTable 3-45
 XpsCoserverTable 3-46
 XpsDbsliceDbospaceTable 3-47
 XpsDbsliceTable 3-48
 Tip icons Intro-7
 Traps
 example 2-5
 general description 1-9
 Informix implementation 2-5

U

UNIX operating system, default
 locale for Intro-4
 Users, types of Intro-3
 Utility, onstat 2-6

W

Warning icons Intro-7
 Windows, default locale for Intro-4

X

XPS MIB
 location in hierarchy 2-32
 reference 3-45
 xpsCogroupMemberTable 3-45
 xpsCogroupTable 3-45
 xpsCoserverTable 3-46
 xpsDbsliceDbospaceTable 3-47
 xpsDbsliceTable 3-48
 XPSMIB registry argument 2-24
 X/Open compliance level Intro-14